

ALTIBASE® HDB™ Tool & Utilities

iLoader User's Manual

Release 6.5.1

May 28, 2015



ALTIBASE HDB Tools & Utilities iLoader User's Manual

Release 6.5.1

Copyright © 2001~2015 Altibase Corporation. All rights reserved.

This manual contains proprietary information of Altibase® Corporation; it is provided under a license agreement containing restrictions on use and disclosure and is also protected by copyright patent and other intellectual property law. Reverse engineering of the software is prohibited.

All trademarks, registered or otherwise, are the property of their respective owners

Altibase Corporation

10F, Daerung PostTower II, 182-13,

Guro-dong Guro-gu Seoul, 152-847, South Korea

Telephone: +82-2-2082-1000 Fax: 82-2-2082-1099

Homepage: <http://www.altibase.com>

Content

Preface	iv
About This Manual.....	v
Audience	v
Software Environment	v
Organization	v
Documentation Conventions.....	v
Related Documents.....	viii
Online Manuals	viii
Altibase Welcomes Your Comments.....	viii
1. iLoader Overview	1
1.1 Introducing iLoader	2
1.1.1 What is iLoader?.....	2
1.1.2 Uses.....	2
1.1.3 Functionality	2
1.1.4 Advantages.....	2
1.1.5 How to Install iLoader	2
1.1.6 iLoader Settings	3
1.1.7 Environment Variables	4
2. Using iLoader	7
2.1 Command-Line Options	8
2.2 General Options	9
2.2.1 Limitations of Options	13
2.2.2 LOB Option	14
2.3 Performance Options.....	19
2.3.1 Atomic Array INSERT	20
2.3.2 Direct-Path INSERT	21
2.4 Using iLoader in Batch Mode.....	23
2.4.1 Creating FORM Files	23
2.4.2 Downloading Data.....	24
2.4.3 Uploading Data	24
2.4.4 Execution Result Code.....	26
2.4.5 Using iLoader for Remote Database Access	26
2.5 Using iLoader in Interactive Mode.....	29
2.5.1 Starting iLoader.....	29
2.5.2 Creating FORM Files	29
2.5.3 Downloading Data.....	30
2.5.4 Uploading Data	30
2.5.5 Execution Result Code.....	30
2.5.6 Remote Access in Interactive Mode.....	30
2.6 Online Help and Other Options	33
2.6.1 Help	33
2.6.2 Other Options	34
3. FORM Files	37
3.1 About FORM Files.....	38
3.1.1 Writing SEQUENCE Statements	38
3.1.2 Modifying Date Format Strings in a FORM File.....	39
3.1.3 Writing Condition Clauses.....	43
3.1.4 Handling TIMESTAMP Columns	44
4. Troubleshooting and FAQs	53
4.1 Troubleshooting	54
4.1.1 Record Upload Failure	54
4.1.2 FORM File Parsing Errors	54
4.1.3 Performance Issues	55
4.2 FAQs	57

Preface

About This Manual

This manual describes how to use the iLoader utility.

Audience

This manual has been prepared for the following ALTIBASE HDB users:

- database administrators
- performance managers
- database users
- application developers
- technical support workers

It is recommended that those reading this manual possess the following background knowledge:

- basic knowledge in the use of computers, operating systems, and operating system utilities
- experience in using relational databases and an understanding of database concepts
- computer programming experience
- experience in database server, operating system or network administration

Software Environment

This manual has been prepared assuming that ALTIBASE HDB 6 is used as the database server.

Organization

This manual is organized as follows:

- [Chapter1: iLoader Overview](#)
- [Chapter2: Using iLoader](#)
- [Chapter3: FORM Files](#)
- [Chapter4: Troubleshooting and FAQs](#)

Documentation Conventions









This section describes the conventions used in this manual. Understanding these conventions will make it easier to find information in this manual and other manuals in the series.


There are two sets of conventions:

- syntax diagrams
- sample code conventions

Syntax Diagrams

This manual describes command syntax using diagrams composed of the following elements::

Elements	Meaning
	The start of a command. If a syntactic element starts with an arrow, it is not a complete command.
	The command continues to the next line. If a syntactic element ends with this symbol, it is not a complete command.
	The command continues from the previous line. If a syntactic element starts with this symbol, it is not a complete command.
	The end of a statement.
	Indicates a mandatory element.
	Indicates an optional element.
	Indicates a mandatory element comprised of options. One, and only one, option must be specified.
	Indicates an optional element comprised of options.

Elements	Meaning
	<p>Indicates an optional element in which multiple elements may be specified. A comma must precede all but the first option.</p>

Sample Code Conventions

The code examples explain SQL, stored procedures, iSQL, and other command line statements.

The printing conventions used in the code examples are described in the following table.

Rules	Meaning	Example
[]	Indicates an optional item.	<pre>VARCHAR [(size)] [[FIXED] VARIABLE]</pre>
{ }	Indicates a mandatory field for which one or more items must be selected.	<pre>{ENABLE DISABLE COMPILE }</pre>
	Argument indicating optional or mandatory fields.	<pre>{ENABLE DISABLE COMPILE } [ENABLE DISABLE COMPILE]</pre>
. . .	Indicates that the previous argument is repeated, or that sample code has been omitted.	<pre>iSQL> select e_lastname from employees; E_LASTNAME ----- Moon Davenport Kobain . . . 20 rows selected.</pre>
Other symbols	Symbols other than those shown above are part of the actual code.	<pre>EXEC :p1 := 1; acc NUMBER(11,2);</pre>
Italics	Statement elements in italics indicate variables and special values specified by the user.	<pre>SELECT * FROM table_name; CONNECT userID/password;</pre>
Lower Case Characters	Indicate program elements set by the user, such as table names, column names, file names, etc.	<pre>SELECT e_lastname FROM employees;</pre>
Upper Case Characters	Keywords and all elements provided by the system appear in upper case..	<pre>DESC SYSTEM.SYS_INDICES_;</pre>

Related Documents

For more detailed information, please refer to the following document.

- ALTIBASE HDB Installation Guide
- ALTIBASE HDB Administrator's Manual
- ALTIBASE HDB Replication Manual
- ALTIBASE HDB Precompiler User's Manual
- ALTIBASE HDB ODBC Reference
- ALTIBASE HDB Application Program Interface User's Manual
- ALTIBASE HDB iSQL User's Manual
- ALTIBASE HDB Utilities Manual
- ALTIBASE HDB Error Message Reference

Online Manuals

Online versions of our manuals (PDF or HTML) are available from Altibase's Customer Support site (<http://support.altibase.com/>).

Altibase Welcomes Your Comments

Please let us know what you like or dislike about our manuals. To help us with future versions of our manuals, please tell us about any corrections or classifications that you would find useful.

Include the following information :

- The name and version of the manual that you are using
- Any comments that you have about the manual
- Your name, address, and phone number

When you need an immediate assistance regarding technical issues, please contact Altibase's Customer Support site(<http://support.altibase.com/>).

Thank you. We appreciate your feedback and suggestions.

1 iLoader Overview

1.1 Introducing iLoader

1.1.1 What is iLoader?

iLoader is a utility provided by Altibase for downloading or uploading data in ALTIBASE HDB in units of tables. Downloaded data will be saved as a text file, and the FORM file containing the structure information of the table is necessary.

1.1.2 Uses

iLoader is mostly used for database migration or when backing up tables. However, because database schema and catalog information are not saved, care must be taken when using iLoader as a backup utility.

1.1.3 Functionality

- FORM file Creation
For creating FORM files for storing information about tables to be downloaded or uploaded.
- Downloading Data
FORM files are used to save the database table data in files.
- Uploading Data
Using FORM files, the data saved in the files are uploaded to the relevant database tables.

1.1.4 Advantages

The advantages of iLoader are as follows.

- Data can be uploaded from one or more files.
- Multiple input records can be uploaded to a single table.
- Data can be uploaded to multiple tables at once.
- Data can be appended to tables that already contain data, or can replace the data therein.
- Data input and management can be made more systematic.

1.1.5 How to Install iLoader

iLoader is automatically installed when the ALTIBASE HDB package is installed. The executable file is located in:

```
$ALTIBASE_HOME/bin
```

1.1.6 iLoader Settings

In order to connect to the server, iLoader requires the following information:

- `ALTIBASE_HOME`
A path to a server or client installation
- `server_name`
The name (or IP address) of a computer on which ALTIBASE HDB Server is running
- `port_no`
The port number to be used when connecting via TCP or IPC
- `user_id`
a User ID registered in the database
- `password`
The password corresponding to the User ID
- `NLS_USE`
The character set with which to display retrieved data to the user

`ALTIBASE_HOME` can only be set using an environment variable, while the other settings may be made using command-line options. (For detailed information, please refer to "Batch Mode".)

The `ALTIBASE_HOME` environment variable must be set in order to use iLoader. This is typically set automatically when the server is installed, but, in the case of the client, must be set manually by the user. We strongly suggest that you verify that this setting has been made properly, as the application may not run correctly if this setting is not made.

`port_no` and `NLS_USE` can be set using the corresponding environment variables or the server settings file (`altibase.properties`). If these settings are made via all three methods, they will take priority as follows, in descending order:

1. command-line options
2. environment variables
(`ALTIBASE_PORT_NO`, `ALTIBASE_NLS_USE`)
3. server settings file (`altibase.properties`)

Therefore, when it is desired to connect using options other than those that have been previously set, the command-line options can be used, thus making it unnecessary to change the settings in the server settings file or the environment variables.

If these options have not been set, when iLoader is executed for the first time, the user will be prompted to enter the corresponding variables. At this time, it is essential to enter values that are valid and follow the proper format, otherwise iLoader may not run properly.

However, if the `NLS_USE` option in particular has not been set, no command prompt will appear at

1.1 Introducing iLoader

the time of execution. Instead, US7ASCII will be used, and a connection attempt will be made. In such instances, if the server is not using US7ASCII, the application will not execute properly, or some of the users' data could become corrupted. Thus it is paramount that NLS_USE be set to the value that matches the usage environment.

In order to ensure stable iSQL operation, we strongly recommend that the following environment variables be set:

- ALTIBASE_HOME: the path to a server or client installation
- ALTIBASE_PORT_NO: the port number to use to connect to the server
- ALTIBASE_NLS_USE: the character set to use to display retrieved data to the user
- PATH: the path containing the executable file, which must equal \$ALTIBASE_HOME/bin

1.1.7 Environment Variables

1.1.7.1 ALTIBASE_HOME

This is used to set the directory in which the package is installed.

In the case of MS Windows, this is set automatically when the server is installed, but when the client is installed, it is not set automatically due to the risk of conflict with the corresponding environment variable for the server. It must therefore be set manually by the user at the time that the client is installed.

This environment variable must be set in order to use iLoader.

Ex)

```
Windows (Server): 'set ALTIBASE_HOME=C:/Program Files/Altibase/
Altibase5_Server/altibase_home',
Windows (Client): 'set ALTIBASE_HOME=C:/Program Files/Altibase/
Altibase5_Client/altibase_home_client')
```

1.1.7.2 ALTIBASE_PORT_NO

This indicates the port number on the server with which a connection is to be established. This can be set using the -PORT option or altibase.properties.

If no designated port number can be found (in descending order of precedence) in the -PORT option, in the environment variable ALTIBASE_PORT_NO, or in altibase.properties, a prompt to enter the port number will appear.

1.1.7.3 ALTIBASE_SSL_PORT_NO

The port number of the server iLoader is to connect to on SSL/TLS.

The -PORT option, environment variables, ALTIBASE_SSL_PORT_NO, the properties in the altibase.properties file take priority in this order as the port number in SSL. On omission, the command prompt asks the user to enter the port number.

1.1.7.4 ALTIBASE_NLS_USE

This sets the character set that is used when data are downloaded or uploaded.

- When downloading: data received from the server are saved in the specified character set.
- When uploading: sets the character set for data to be transmitted to the server.

Note: when uploading data, if the character set of the database is different from the value specified using the ALTIBASE_NLS_USE environment variable, the data may not be uploaded normally. Please be sure to set the correct value for this variable.

- One of the following character sets may be set to ALTIBASE_NLS_USE.
 - US7ASCII
 - KO16KSC5601
 - MS949
 - BIG5
 - GB231280
 - UTF8
 - SHIFTJIS
 - EUCJP

If the character sets used by the server and client are different, the character data will be converted accordingly. It is recommended to synchronize the character sets between server and client before using iLoader for two reasons as follows :

- It takes additional CPU time to convert character data according to the character set.
- If the character data are converted to target character set, data loss can occur.

The client character set can also be set using the -NLS_USE option or in altibase.properties. If NLS_USE is not specified using the -NLS_USE option, the environment variable ALTIBASE_NLS_USE, or altibase.properties (in descending order of precedence), then US7ASCII is used as the default character set.

1.1 Introducing iLoader

2 Using iLoader

This chapter explains how to use iLoader. The various options provided by ALTIBASE HDB can be used with iLoader. iLoader can run in batch mode or in interactive mode. Command-line options are used when running iLoader in batch mode.

2.1 Command-Line Options

The command-line options supported by ALTIBASE HDB include general options and options for improving performance.

- [General Options](#)
- [Performance Options](#)

The general options and performance options are all listed below. They are explained in the next section.

```

iloader [-h]
  [-s server_name] [-u user_name] [-p password]
  [-port port_no] [-silent] [-nst] [-displayquery]
  [-NLS_USE nls_name]
  [-prefer_ipv6]
  [-ssl_ca CA_file_path | -ssl_capath CA_dir_path]
  [-ssl_cert certificate_file_path]
  [-ssl_key key_file_path]
  [-ssl_verify]
  [-ssl_cipher cipher_list]
  [{ in | out | formout | structout | help }
  [-d datafile or datafiles] [-f formatfile]
  [-T table_name] [-F firstrow] [-L lastrow]
  [-t field_term] [-r row_term] [-mode mode_type]
  [-commit commit_unit] [-bad badfile]
  [-log logfile] [-e enclosing] [-array count]
  [-replication {true | false}] [-split number]
  [-readsize size] [-errors count]
  [-lob lob_option_string] [-atomic]
  [-parallel count] [-direct]
  [-rule csv]]

```

2.2 General Options

iLoader is run with the following options. Where applicable, default values are shown.

Factor	Description
-S -s <i>server_name</i>	<p>The host name of the server.</p> <p>This option specifies the name(or IP address) of the computer on which the ALTIBASE HDB server is running.</p> <p>If connection is attempted while the ISQL CONNECTION environment variable is set to IPC or UNIX, and the remote server is specified for this option, iSQL ignores the ISQL CONNECTION specification and connects to the remote server via TCP, and outputs a warning message that the ISQL CONNECTION specification has been ignored. It can be a host name, an IPv4 address, or an IPv6 address. An IPv6 address must be enclosed by a left square bracket([) and a right square bracket(]).</p> <p>For example, in the case of localhost (meaning this computer), localhost can be specified as the host name, 127.0.0.1 as the IPv4 address, or [::1] as the IPv6 address. For more information about the IPv6 address notation, please refer to the <i>ALTIBASE HDB Administrator's Manual</i>.</p>
-U -u <i>user_name</i>	The user ID
-P -p <i>password</i>	The user password
-PORT <i>port_no</i>	<p>Specifies the port number for connecting via TCP/IP or IPC. However, when connecting in a Unix environment via IPC, this option must not be specified. On specification, a warning message is output. After a warning message is output, connection to the server is made. To connect via TCP, first set 'ISQL_CONNECTION=TCP' on the client and then enter the PORT_NO.</p> <p>To connect via IPC in a Windows environment, set the environment variable 'ISQL_CONNECTION=IPC' and specify the port number using one of the following:</p> <ul style="list-style-type: none"> • the -PORT option • the ALTIBASE_IPC_PORT_NO environment variable • the IPC_PORT_NO property in altibase.properties <p>If the environment variable ISQL_CONNECTION is not set to IPC and the -PORT option is omitted, the port number will be checked for first in the environment variable ALTIBASE_PORT_NO and then in the PORT_NO property in altibase.properties, and if it is not set in either of those places, a prompt to enter it will be raised.</p>

2.2 General Options

Factor	Description
-NLS_USE <i>charset</i>	<p>This is the character set displayed to the user when selecting data. Specifies the encoding on the terminal from which iSQL is run.</p> <ul style="list-style-type: none"> • US7ASCII • KO16KSC5601 • MS949 • BIG5 • GB231280 • MS936 • UTF8 • SHIFTJIS • EUCJP <p>On omission, the environment variables, ALTIBASE_NLS_USE and alti-base.properties are referenced in turn. If no value is set, the default character set US7ASCII is used.</p>
-prefer_ipv6	<p>This option determines the IP address to be connected first when a host name is given for the -s option.</p> <p>If this option is specified and a host name is given for the -s option, this means that resolving the host name to the IPv6 address is preferred.</p> <p>If this option is omitted, <code>iloder</code> connects to the IPv4 address by default.</p> <p>If it fails to connect to the preferred IP version address, an attempt is made to connect using the other IP version address.</p> <p>For example, when <code>localhost</code> is given for the -s option and this option is specified, <code>iloder</code> first tries to connect to the <code>:::1</code> IPv6 address. If this attempt fails, <code>iloder</code> proceeds to connect to the <code>127.0.0.1</code> IPv4 address.</p>
-ssl_ca CA_file_path	Specifies the location of the certification authority (CA) certificate in which the public key of the ALTIBASE HDB server to be connected to is incorporated.
-ssl_cacpath CA_dir_path	Specifies the directory under which the certification authority (CA) certificate in which the public key of the ALTIBASE HDB server to be connected is incorporated.
-ssl_cert certificate_file_path	Specifies the location of the client authentication file.
-ssl_key key_file_path	Specifies the location of the client private key file.
-ssl_verify	Verifies the certificate the client receives from the server.
-ssl_cipher cipher_list	Specifies a cipher list for SSL encryption. Please refer to the SSL_CIPHER_LIST property in the <i>General Reference</i> .

Factor	Description
in out formout structout help	<p>Sets the direction in which to copy data (it is essential that only one is set)</p> <ul style="list-style-type: none"> • in: Copy from a file to a database table. • out: Copy from a database table to a file. • formout: Make a table format file (FORM file). • structout: Performs a function similar to that of formout. Used to create a structure matching that of a given table. (Used when creating a client application.) • help: Explain how to use help.
-T <i>table_name</i>	<p>The name of the table to be copied. If you use double quotation marks to enclose this, this is case-sensitive when you execute iLoader in interactive mode. Since the table name is already written in the FORM file, this option is ignored when uploading or downloading data.</p>
-d <i>datafile(datafiles)</i>	<p>The full path of the data file used when copying data from the database to the file or from the file to the database. Not used with formout.</p> <p>A maximum of 32 filenames can be entered. A consecutive series of files can be specified and used only when uploading data. When multiple files are specified using the -d option, they are uploaded in the order that the filenames are entered.</p> <p>Moreover, when this option is used together with the parallel option during a download operation, at least as many files as the number specified in the parallel option are created.</p>
-rule csv	<p>This specifies the format of the data file as csv. This option cannot be used in conjunction with the -t or -e options. Otherwise, an error will be raised. If none of the -t, -r, -e or -rule csv options are set, csv is used by default.</p>
-f <i>formatfile</i>	<p>The full path of formatfile, created by a previous call to iLoader.</p>
-F <i>firstrow</i>	<p>The line number of the first row to be copied (default is 1). This option is meaningful only when uploading data.</p>
-L <i>lastrow</i>	<p>The line number of the last row to be copied (default is the line number of the last row). This option is meaningful only when uploading data.</p>

2.2 General Options

Factor	Description
-t <i>field_term</i>	<p>The delimiter between fields. The default is '^'. %t signifies a tab character, %n signifies a newline character and %r signifies a carriage return.</p> <p>The -t, -r and -e options must be different from each other. e.g.) -t ^%t</p> <p><Caution></p> <p>It is inadvisable to use characters that are interpreted on the command line, such as:</p> <pre>' " \ &</pre> <p>as delimiters.</p> <p>When using delimiters (for example "#") at the iLoader prompt, they can be entered as -t # or "#". At a general command prompt, they can be entered as -t #, '# ' or "#".</p>
-r <i>row_term</i>	<p>row terminator (default is '\n')</p> <p>The details are the same as for the -t option.</p>
-e <i>enclosing_term</i>	<p>Block delimiter for enclosing fields.</p> <p>The details are the same as for the -t option.</p>
-lob <i>lob_option_string</i> (see LOB Option)	<p>Because the maximum allowable size of LOB data is 4GB, problems may arise when LOB data larger than 2GB are saved on 32-bit operating systems. Therefore, this option can be used to specify how to handle LOB type data. If this option is not specified, LOB columns will be handled just like other columns.</p>
-replication true false	<p>This option specifies whether to perform replication when uploading data. If this option is omitted, the default is to perform replication, so in order to prevent replication, this option must explicitly be set to false.</p>
-mode <i>mode_type</i>	<ul style="list-style-type: none"> • APPEND: This adds data to existing tables. (default) • REPLACE: This uses the DELETE statement to delete all data from the existing table and then populate the table with the new records. • TRUNCATE: Similar to REPLACE, this deletes all data from the existing table and then populates the table with the new records, however it uses the TRUNCATE statement to do so. TRUNCATE affords some performance benefits compared to REPLACE, but cannot be performed on tables that are associated with triggers.
-bad <i>badfile</i>	<p>If one or more errors occur during an upload operation, this option saves rows that were not uploaded in <i>badfile</i>. Not saved if not specified.</p> <p>If stdout or stderr (must be in lowercase) is specified for this option, no file is created. Instead, the rows are output to stdout (standard out) or stderr (standard error).</p>

Factor	Description
<code>-log logfile</code>	Maintains a record of iLoader execution while iLoader is running. The start time, end time, number of target rows, number of processed rows, number of erroneous rows, and error details are recorded here. It will not be saved unless specified. If <code>stdout</code> or <code>stderr</code> (must be in lowercase) is specified for this option, no file is created. Instead, the log information is output to <code>stdout</code> (standard out) or <code>stderr</code> (standard error).
<code>-split n</code>	Specifies the number of records to copy to each file (only meaningful when used with the <code>-out</code> option). After the command is executed, multiple backup files, each storing a number of records equal to <i>n</i> and having the names <code>datefile.dat0</code> , <code>datefile.dat1</code> , etc... will have been created.
<code>-errors count</code>	This specifies the maximum number of allowable errors when iLoader is executed with the <code>-in</code> option. If the number of errors exceeds the number specified here, execution terminates. If this option is omitted, the default is 50. If this value is set to 0, execution continues regardless of the number of errors. The number of errors occurring during the uploading operation may exceed the number specified here. When this option is used in conjunction with the <code>-parallel</code> option, if the number of errors exceeds the specified value for one of multiple threads executing in parallel, all threads are terminated.
<code>-partition</code>	If the table specified using the <code>-T</code> option is a partitioned table, a number of FORM files equal to the number of partitions in the table will be generated. The name of each FORM file will have this structure: <code>[formfile_name.partition_name]</code> . If the specified table is not a partitioned table, one FORM file, named <code>formfile_name</code> , will be generated.

- If the `-S`, `-U` and `-P` command-line options are omitted, the user will be prompted to enter the values of these options manually at the time of execution.

```
iSQL> CREATE TABLE test (i1 integer);
Create success.

$ iloader formout -T test -f test.fmt
-----
      Altibase Data Load/Download utility.
      Release Version 6.1.1.1
      Copyright 2000, ALTIBASE Corporation or its subsidiaries.
      All Rights Reserved.
-----
Write Server Name (default:localhost) :
Write UserID : sys
Write Password :
ISQL_CONNECTION : TCP
```

- If “i-loader” is entered without any options at a shell prompt, the iLoader> prompt appears, and work can be conducted in interactive mode.
- All of the options described above are case-sensitive except for `-S`, `-U`, and `-P`.

2.2 General Options

- The `-in` | `-out` | `-formout` option must be entered before any of the other command options.
- For further information about SSL connection, please refer to Chapter 2. Connecting and Disconnecting in the *iSQL User's Manual*.

2.2.1 Limitations of Options

Field delimiters, row delimiters and block delimiters cannot be subsets of each other. In other words, the field delimiter must not contain the row delimiter, and the row delimiter must not contain the field delimiter. Moreover, column values cannot contain these delimiters.

For example, if the field delimiter is `'-'` and the row delimiter is `'-#'`, a row having 3 columns would be displayed as follows:

```
Honggildong-027551234-Seoul-#
```

In this case, the third `'-'` would be recognized as another field delimiter, so the row would be handled as though it had 4 columns and no row delimiter.

In the case below, although the field delimiter, which is `'-'`, is not a subset of the row delimiter, which is `'##'`, the second and third dashes (`'-'`), which are part of the data in the second column, are erroneously recognized as field delimiters.

```
Honggildong-02-755-1234-Seoul##
```

Therefore, the delimiters must be selected carefully because of the possibility that they will be incorrectly handled.

In Windows, lines end with both a line feed and a carriage return (`'\r\n'`). So when you write a datafile manually and upload it, `'\r\n'` must be specified for the row terminator.

For example, when uploading a data file which is in csv format with `'\r\n'` for a row terminator, the following options would be specified.

```
iload in [-T table_name] [-f formatfile] [-d datafile] [-r %r%n] [-rule csv]
```

2.2.2 LOB Option

The user can specify how LOB columns are handled by entering *lob_option_string* after the `-lob` option. To specify multiple keywords (see below), use the `-lob` option repeatedly on the same line, each `-lob` option being followed by its own *lob_option_string*, enclosed in double quotation marks.

The keywords for *lob_option_string* are as follows:

The user can determine how a LOB column is processed by specifying *lob_option_string* after `-lob` option.

- `use_lob_file`
- `lob_file_size`
- `use_separate_files`
- `lob_indicator`

2.2.2.1 use_lob_file

```
use_lob_file = {yes|no}
```

Determines whether LOB data expressions refer to external files (LOB files).

Either value can be used when iLoader is copying data in either direction ("in" or "out").

For information on LOB file naming conventions, please refer to the description of the `lob_file_size` option.

2.2.2.2 lob_file_size

```
lob_file_size = file_size
```

Specifies the maximum size of a LOB file. If the `use_lob_file` option is set to `yes` and this option is not specified, the size of the external file is only limited by the operating system's file size limit. When the file size is limited by the operating system or the platform, it is recommended that this option be set to 2 GB or less on platforms on which the long data type is 4 bytes.

This option is applicable only when the iLoader data copy direction is "out". iLoader ignores this option when the data copy direction is "in". When the data copy direction is "in", the size of the first LOB data file is taken as `lob_file_size`.

If this option is set without the `use_lob_file` option being specified, it is inferred that `use_lob_file = yes`.

If the size of LOB data to be dumped exceeds the size specified in this option, a new file is created, and the data dump continues.

The file size is represented in 'number + unit' format. The number can be represented to one decimal place. The number cannot be 0.

The units that can be used for the file size are "T" and "G". "T" indicates terabytes and "G" indicates gigabytes. If no units are specified, gigabytes are used by default.

The name of each LOB file is determined by removing the filename extension from the original data file name and appending `_serialNumber.lob` thereto. The serial number has 9 digits. If the number of digits in the serial number is less than 9, the leftmost positions of the serial number are filled with 0's (zeroes). The serial numbers start at 1. If a data file is split into several files using the `-split` option, a data file number is appended to each LOB file name.

For example, if the option

```
-d dump.dat -lob "lob_file_size-uG".
```

is specified, the following LOB files are created:

Total amount of LOB data: T GB

Size of each resulting file: u GB

```
dump_000000001.lob (u Gbytes)
dump_000000002.lob (u Gbytes)
...
dump_n.lob (T - un GBytes)
  where n = int(T / u), preceded by 0
```


2.2 General Options

2.2.2.3 use_separate_files

`use_separate_files = {yes | no}`

When processing LOB files, this option determines whether to save each LOB data item (i.e. contents of one cell) in a separate file. This option assumes that `use_lob_file` is set to `yes`.

If this option is set to `yes` and `lob_file_size` is also specified, an error occurs.

When this option is set, folders having the same names as tables and columns are created and LOB data from these columns are saved in data files in numeric order according to row. The row numbers start from 1 and have 9 digits. If the number of digits in the row number is less than 9, the leftmost positions of the row number are filled with 0's (zeroes).

For example, if columns C1 and C3 of table t1, which has 3 columns, are LOB type columns, and

```
-d d.dat -lob "use_separate_files=yes"
```

is specified, the following LOB files are created.

- t1/C1/000000001.lob
- t1/C1/000000002.lob
- t1/C3/000000002.lob
- t1/C3/000000002.lob

When this option is set, the path of the LOB file is written in the corresponding data cell in the LOB column in the data file. However, if the LOB data are NULL, the address of the LOB file isn't written, and no LOB file is created.

Note: When downloading data using `-lob "use_separate_files=yes"`, the directory, in which LOB files is located, which is written in a data file is represented relative to the path given with `-d` option. But, if you change the relative path to the absolute path manually in the data file and upload it, the file path set specified by `-d` option will be ignored.

In other words, if an absolute path is represented for the directory in which LOB files is located, `iLoader` utility uses the absolute path. On the contrary, if a relative path is represented for the directory, `iLoader` utility uses the path made by attaching the relative path in the data file to the path given with `-d` option.

2.2.2.4 lob_indicator

`lob_indicator = char_sequence`

This option specifies a block delimiter that denotes a pointer for indicating the offset and size of a LOB file.

It can be used regardless of whether the data copy direction in `iLoader` is in or out.

The default value is `%%`.

Up to 10 characters can be used. However, `%t`, `%n` and `%r` are each regarded as one character.

`%t` indicates a tab, `%n` indicates a newline character and `%r` indicates a carriage return.

This option cannot have the same value specified for the -t, -r or -e options.

It is recommended that characters that are interpreted on the command line, such as:

```
' " \ &
```

not be used as delimiters.

It is assumed that use_lob_file = yes if it is not specified.

When the data copy direction in iLoader is in and use_lob_file = yes, if a LOB column in a data file does not start with the character sequence specified by lob_indicator, the data row containing that LOB column is treated as an erroneous row.

2.2.2.5 Examples

To dump LOB data to external files, such as t1_000000001.lob, t1_000000002.lob, etc. which are 1.5 GB in size:

```
$ iloader out ... -f t1.fmt -d t1.dat -lob "lob_file_size=1.5G"
```

To dump LOB data to a single file named t1.lob:

```
$ iloader out ... -f t1.fmt -d t1.dat -lob "use_lob_file=yes"
```

```
$ iloader out ... -f t1.fmt -d t1.dat -lob "use_lob_file=yes" -lob
"lob_file_size=1G"
```

```
$ iloader out ... -f t1.fmt -d t1.dat -lob "lob_indicator=%$LOB$%"
```

2.2.2.6 Data File Format for LOB Data

When downloading a column containing LOB data, an offset:size combination which points to the location of LOB data in an external file is written to the data file.

If the offset:size combination, which points to LOB data, is not expressly specified, then iLoader looks in the data file for the pointer to the position of the LOB data in the LOB file after a %% delimiter.

Ex)

```
$ cat t1.fmt
table t1
{
"I1" integer;
"I2" blob;
"I3" char (10);
}
DATA_NLS_USE=KO16KSC5601

$ iloader out ... -f t1.fmt -d t1.dat -lob "lob_file_size=3G"
$ ls
t1_000000001.lob t1_000000002.lob t1.dat t1.fmt


$ cat t1.dat
1, "%%0:2000000000", "Terminator3"
2, "%%2000000000:1800000000", "SixSense"
$
```

The actual LOB data are downloaded to a LOB file, regardless of whether LOB offset and size informa-

2.2 General Options

tion is provided between field delimiters (or between a pair of block delimiters, if using block delimiters).

This is illustrated in the following figure:



When null LOB data are downloaded to a data file, there will be no data between the field separators (or between the pair of block delimiters, if appropriate) at the position of the corresponding LOB data within the data file. LOB data of size 0 are also stored in the same way. (ALTIBASE HDB internally handles LOB data of size 0 as NULL.)

If the `use_separate_files` option is specified, the data files are organized as follows:

```
t1/I1/000000001.lob, t1/I2/000000001.lob, t1/I3/000000001.lob
t1/I1/000000002.lob, t1/I2/000000002.lob, t1/I3/000000002.lob
t1/I1/000000003.lob, t1/I2/000000003.lob, t1/I3/000000003.lob
'''
```

In the above example, all of the columns contain LOB data.

If the LOB data to be stored in a LOB file are NULL, no characters are stored at the corresponding LOB data position in the data file, as can be seen in the fourth row above.

2.3 Performance Options

The following options can realize considerable performance gains when running iLoader.

Factor	Description
-array <i>array_size</i>	<p>To increase the speed of a data uploading (“in”) operation, data read from a file are first organized into an array before being sent to the server.</p> <p>Performance is increased because the number of times that communication with the server must be established is decreased.</p> <p>However, if this value is set excessively high, it can have the opposite effect.</p> <p>If a LOB column exists, -array is ignored.</p>
-commit <i>commit_unit</i>	<p>When uploading data, this option determines how many records are committed at one time after being inserted. By default, 1000 records are committed after being inserted.</p> <p>If <i>commit_unit</i> is set to 0, the application runs in NON-AUTOCOMMIT mode, in which the commit operation takes place only after all data have been inserted.</p> <p>If <i>commit_unit</i> is set to 1, the application runs in AUTOCOMMIT mode, in which a commit operation takes place for every record at the time that it is inserted.</p> <p>When this option is used together with the array option, the commit operation takes place after a number of records equal to <i>array_size</i> * <i>commit_unit</i> have been inserted.</p>
-atomic	<p>This option is set to use the Atomic Array INSERT option. Atomic Array INSERT realizes better performance than Array Insert because Atomic Array INSERT handles a number of Insert statements (up to the size of the array) as a single transaction.</p> <p>This option must be used together with the -array option. Additionally, tables that contain LOB type columns cannot be handled using this option.</p> <p>Furthermore, this option is useful only when uploading data.</p>
-direct [log nolog] (See Direct-Path INSERT)	<p>This option is for use with the Direct-Path INSERT when uploading data to a disk table.</p> <p>If neither log nor nolog is specified, log is the default.</p> <p>If using nolog mode, it is essential to back up the table in question. If execution fails in nolog mode, recovery to a normal state will be impossible.</p> <p>If loading tables for which there are restrictions (see Restrictions for Direct-Path INSERT), execution will automatically switch to the atomic option.</p> <p>If the -array option has not been set, the size of the array will automatically be set to the maximum possible size (=USHRT_MAX-1, or 65535).</p> <p>If the -commit option is omitted, its value will be set to 1.</p>

2.3 Performance Options

Factor	Description
<code>-parallel count</code>	<p>This specifies the number of threads that can operate at the same time. A number of threads can be created and executed in parallel up to the specified value, the maximum of which is 32. When downloading, a number of files equal to the specified value is created, and the data are saved therein.</p> <p>When downloading with only the <code>-parallel</code> option set, the performance of repeated bind and fetch operations may be reduced. Therefore, when downloading data, the <code>-parallel</code> and <code>-array</code> options should be used together.</p> <p>If a LOB column is present, this option is ignored.</p> <p>When uploading with the <code>-parallel</code> option, iLoader creates <code>count + 1</code> connections, and when downloading with this option, iLoader always creates two connections. Therefore, when uploading or downloading with this option via IPC, the value in the <code>IPC_CHANNEL_COUNT</code> property in <code>altibase.properties</code> must be equal to or greater than the number of these connections.</p>
<code>-readsize integer</code>	<p>When iLoader is executed in "in" mode, this option specifies the amount of data that are read from a file at one time. The size must be greater than 0. The default is 1048576 bytes.</p>

2.3.1 Atomic Array INSERT

The `-atomic` option is used to execute Atomic Array INSERT, which is useful only when uploading data. Atomic Array INSERT can realize faster performance than Array INSERT because Atomic Array INSERT handles a number of Insert statements (up to the size of the array) as a single transaction.

When uploading records using Atomic Array INSERT, if one of the records is not successfully uploaded, the records will instead be uploaded using Array INSERT. In other words, the result of Atomic Array INSERT is the same as Array INSERT. Moreover, Atomic Array INSERT provides much better performance than Array INSERT. For this reason, the use of Atomic Array INSERT is recommended.

2.3.1.1 The Difference between Atomic Array INSERT and Array INSERT

A comparison of Atomic Array INSERT and Array INSERT reveals the following:

Array INSERT executes individual statements separately, whereas Atomic Array INSERT can combine several statements and handle them as though they were a single statement.

While Array INSERT's original advantage is low communication overhead, Atomic Array INSERT realizes even faster performance because it reduces the number of statements.

Array INSERT and Atomic Array INSERT are compared in the following table.

Table 2-1 Differences between Array INSERT and Atomic Array INSERT

Characteristic	Array INSERT	Atomic Array INSERT
Number of Statements	Number of Array Elements	One

Characteristic	Array INSERT	Atomic Array INSERT
Number of Results	Number of Array Elements	One
Number of Results (when an error occurs)	Number of Array Elements	Number of Array Elements
Transmission Speed	Fast	Very Fast

2.3.1.2 Atomic Array INSERT Limitations

The following limitations govern the use of Atomic Array INSERT:

Note: N=number of array elements

Table 2-2 Atomic Array INSERT Limitations

	Array INSERT	Atomic Array INSERT
Foreign Key	Operates Normally	Operates Normally
Unique Key	Operates Normally	Operates Normally
Not null	Operates Normally	Operates Normally
Check	Operates Normally	Operates Normally
Trigger Each Row	Executed N times	Executed N times
Trigger Each Statement	Executed N times	Executing Once
Partitioned Table	Operates Normally	Operates Normally
Sequence	Executed N times	Executed N times
SYSDATE	Executed N times	Executing Once
LOB Column	Operates Normally	Atomic attribute is not guaranteed when errors occur.
Procedure	Operates Normally	Operates Normally
SubQuery	A new view is observed every time	The first executed view is observed

2.3.1.3 Atomic Array INSERT: Warning

The `-atomic` option must be used with `[-array array_size]`, and must not be used on tables that include LOB columns. Furthermore, this option is only useful when uploading data.

2.3.2 Direct-Path INSERT

The so-called Direct-Path INSERT has been provided to support the uploading of data into a disk table. Direct-Path INSERT is a method of writing data directly into a data file using a Direct-Path INSERT buffer and a flush manager, bypassing the buffer manager. Moreover, free space in the exist-

2.3 Performance Options

ing extents is not used. Instead, new extents are allocated for a Direct-Path INSERT operation. Consequently, performance is improved, but additional space is required.

You can query the `V$DIRECT_PATH_INSERT` performance view to manage statistics for Direct-Path INSERT. See *Administrator's Manual*.

2.3.2.1 Restrictions for Direct-Path INSERT

The following restrictions apply when uploading data using the Direct-Path INSERT. If the data to be uploaded do not satisfy all of these restrictions, data can be uploaded automatically using Atomic Array INSERT (-atomic option) instead of Direct-Path INSERT (-direct option).

- the table can't have an index (or a Primary Key).
- the table can't be associated with a trigger.
- the table can't have a LOB column.
- the table cannot have CHECK constraints.
- the table cannot have referential integrity constraints.
- replication cannot be performed on the table.
- the table must exist in disk tablespace.

2.3.2.2 Warnings

When processing data using the Direct-Path INSERT, please abide by the following:

- If data upload fails while Direct-Path INSERT operation is being executed in nologging mode ("direct nolog"), it will be impossible to restore the database normally. Therefore, it is critical to back up the relevant table(s) before using nologging mode.
- The Direct-Path INSERT realizes excellent performance when uploading large amounts of data. However, when not handling large amounts of data, the improvement in performance will not be notable.
- Data can be loaded using the Direct-Path INSERT only if the table exists in disk tablespace. Therefore, when using this method to load data into memory tablespaces, the result will be the same as if the -atomic option were used.

2.3.2.3 Example

- To execute direct-path uploading in logging mode with the maximum array size:

```
iloaders in t1.form -d t1.dat -direct [log]
```

- To execute direct-path uploading in nologging mode with the maximum array size:

```
iloaders in t1.form -d t1.dat -direct nolog
```

- To execute direct-path uploading in logging mode with a specified array size:

```
iloaders in t1.form -d t1.dat -array 1000 -direct
```

2.4 Using iLoader in Batch Mode

iLoader can run in interactive mode or in batch mode. When running iLoader in batch mode, command-line options are used.

2.4.1 Creating FORM Files

FORM files provide iLoader with information on the attributes of target tables when data are uploaded or downloaded. This information covers all aspects of table schema except constraints. In order to use iLoader to load data, FORM files containing information about the target tables(s) must first be created.

The syntax for creating FORM files is shown below.

```
iloader formout [-S server_name] [-U user_name] [-P password] [-T
table_name] [-f formatfile]
```

In the following example, table T1 and a corresponding FORM file are created.

```
isQL> CREATE TABLE t1 (
name      VARCHAR(30),
age       INTEGER,
gender    CHAR(1),
etc       NVARCHAR(30));
Create success.

isQL> INSERT INTO t1 VALUES ( 'John Doe', 20, 'M', N'Group A');
1 row inserted.

isQL> INSERT INTO t1 VALUES ('Pham Tan Sang', 30, 'M', N'Group C');
1 row inserted.

isQL> INSERT INTO t1 VALUES ('Alisee Dupoint', 24, 'F', N'Group D');
1 row inserted.

isQL> SELECT * FROM t1;
NAME                AGE      GENDER  ETC
-----
John Doe             20       M       Group A
Pham Tan Sang        30       M       Group C
Alisee Dupoint       24       F       Group D
3 rows selected.

isQL> EXIT

$ iloader formout -s 127.0.0.1 -u sys -p manager -T T1 -f T1.fmt
-----
Altibase Data Load/Download utility.
Release Version 6.1.1.1
Copyright 2000, ALTIBASE Corporation or its subsidiaries.
All Rights Reserved.
-----
ISQL_CONNECTION : TCP

$ cat T1.fmt
table T1
{
"NAME" varchar (30);
"AGE" integer;
```


2.4 Using iLoader in Batch Mode

```
"GENDER" char (1);  
"ETC" nvarchar (30);  
}  
DATA_NLS_USE=KO16KSC5601  
NCHAR_UTF16=YES
```

DATA_NLS_USE can be used to show how downloaded data will be encoded. Normally, when a FORM file is created, the client character set is used.

If the table to be downloaded contains a national character type column, NCHAR_UTF16 will be used. The encoding method that is used when data are saved is UTF-16BE (Big Endian) when NCHAR_UTF16 is set to YES. If set to NO, data will be encoded as CHAR type, and could be lost. The default value is YES.

2.4.2 Downloading Data

Records in the database table that satisfy the conditions specified in the FORM file are saved in text file form. Downloaded data will be saved according to the character set specified using the ALTIBASE_NLS_USE environment variable. If the database character set is different from that specified in ALTIBASE_NLS_USE, the data will be converted. When downloading data, ALTIBASE HDB displays the table name every 5,000 records, and also displays the total number of records after all records have been downloaded. The following syntax is used to download data.

```
iloaders out [-S server_name] [-U user_name] [-P password] [-f format-  
file] [-d datafiles] [-split number] [-array count] [-parallel count]
```

In the following example, the T1.fmt file is used to download data to the T1.dat file.

```
$ iloaders out -s 127.0.0.1 -u sys -p manager -f T1.fmt -d T1.dat
```

```
-----  
Altibase Data Load/Download utility.  
Release Version 6.1.1.1  
Copyright 2000, ALTIBASE Corporation or its subsidiaries.  
All Rights Reserved.  
-----  
ISQL_CONNECTION : TCP  
DATA_NLS_USE: KO16KSC5601  
NCHAR_UTF16 : YES  
  
Total 3 records downloaded(T1)  
  
DOWNLOAD : 11.2320 msec  
  
$ cat T1.dat  
"John Doe",20,"M","Group A"  
"Pham Tan Sang",30,"M","Group C"  
"Alisee Dupoint",24,"F","Group D"
```

2.4.3 Uploading Data

iLoader can be used to upload backup files or files containing edited data to the database.

The data character set must be specified using ALTIBASE_NLS_USE when uploading data. iLoader converts data saved in the character set specified in ALTIBASE_NLS_USE to the database character set and then saves the data. If the database character set and the character set specified using ALTIBASE_NLS_USE are different, the data are converted. If the character set specified in

ALTIBASE_NLS_USE is different from the character set in which the data were actually saved, the data will not be uploaded properly.

When uploading data, the `-atomic` option can be used to perform Atomic Array Insert to realize improved performance. The `-atomic` option must be used with the `-array` option, and it is additionally recommended that the `-commit` option also be used.

When uploading data, iLoader displays the table name every 5,000 records, and also displays the total number of records after all records have been uploaded.

The following syntax is used to upload data.

```
iloader in [-S server_name] [-U user_name] [-P password] [-f format-
file] [-d backup_files] [-mode mode_type] [-F firstrow] [-commit
commit_unit] [-L lastrow] [-array count] [-atomic] [-parallel count]
```

In the following example, the T1.fmt file and the T1.dat file are used to upload data.

```
$ iloader in -s 127.0.0.1 -u sys -p manager -f T1.fmt -d T1.dat -F 1 -L 2
```

```
-----
Altibase Data Load/Download utility.
Release Version 6.1.1.1
Copyright 2000, ALTIBASE Corporation or its subsidiaries.
All Rights Reserved.
-----
ISQL_CONNECTION : TCP
DATA_NLS_USE: KO16KSC5601
NCHAR_UTF16 : YES

UPLOAD : 24.4040 msec

      Load Count   : 2(T1)

$ isql -s 127.0.0.1 -u sys -p manager -silent

iSQL> SELECT * FROM t1;
NAME          AGE          GENDER      ETC
-----
John Doe      20           M            Group A
Pham Tan Sang 30           M            Group C
Alisee Dupoint 24          F            Group D
Yuvraj Kohli  20           M            Group A
Hok Chan      30           M            Group C
5 rows selected.
```

- The table information in the previously created T1.fmt file is referenced to upload the data in the T1.dat file to table T1 of the current database.
- Since the default value of the `-mode` option is APPEND, data are appended to the T1 table. (The REPLACE option uploads data after first deleting all of the data in table T1 of the current database.)
- The 1st and 2nd records are uploaded from the T1.dat file. If 100 and 1000 are specified for the first row and the last row respectively, data in the file from the 100th record to the 1000th record are uploaded.

```
$ iloader in -s 127.0.0.1 -u sys -p manager -f T1.fmt -d T1.dat -array
1000 -commit 1 -atomic
```

- The table information in the T1.fmt file is referenced to upload 1000 records at a time from the

2.4 Using iLoader in Batch Mode

T1.data file to table T1 of the current database using Atomic Array Insert.

2.4.4 Execution Result Code

ALTIBASE HDB displays one of the following execution result codes after using iLoader to download or upload data.

- 0 : Success
- -1 : General Error
- -2 : One or more upload errors have occurred.

0 or -1 is displayed to indicate success or failure, respectively, of a data upload or download operation. -2 is displayed to indicate that the overall upload operation succeeded but that one or more errors occurred.

2.4.5 Using iLoader for Remote Database Access

You can use iLoader to access a remote server. To execute iLoader, the ALTIBASE HDB server must have been started. The options are as follows, and are case-insensitive.

2.4.5.1 Command line options for running iLoader remotely

```
iloader [-H] [-S server_name] [-U user_name] [-P password] [-PORT port_no] [-SILENT] [-NST] [-DISPLAYQUERY]
```

- -H: provides help on how to execute iLoader.
- -S *server_name*: specifies the name (or IP address) of the computer on which the ALTIBASE HDB server is running.
- -U *user_name*: specifies the user ID with which to access the database.
- -P *password*: specifies the password corresponding to the user ID.
- -PORT *port_no*: specifies the port number for communication with the remote server.
- -SILENT: specifies execution in silent mode. In silent mode, nonessential information, such as the copyright notice etc., is not displayed.
- -NST: specifies execution in nst mode. In nst mode, elapsed times are not displayed.
- -DISPLAYQUERY: The user can check hints and conditional clauses specified in a FORM file when executing statements. They are displayed in query format.
- -NLS_USE: specifies the character set to be used when downloading or uploading data. If omitted, the client's environment variable ALTIBASE_NLS_USE and altibase.properties are referred to in sequence, and if still not set, the basic character set (US7ASCII) is used.

The options -S *server_name*, -U *user_name*, -P *password*, and -PORT *port_no* must be directly input at a command prompt when connecting to the remote server.

2.4.5.2 Example

- Remote server (IP 192.168.1.10, PORT_NO: 21300)
- Communication protocol :TCP/IP (ISQL_CONNECTION=TCP/IP)

Remote Server Data

Remote server (192.168.1.10)

```
iSQL> CREATE TABLE departments (
dno          SMALLINT      PRIMARY KEY,
dname        CHAR(30)      NOT NULL,
dep_location CHAR(15),
mgr_no       INTEGER );
Create success.

iSQL> INSERT INTO departments VALUES (5001, 'TECHNICAL', 'Las Vegas', 1);
1 row inserted.

iSQL> INSERT INTO departments VALUES (5002, 'ENGINE DEVT', 'Munich', 10);
1 row inserted.

iSQL> INSERT INTO departments VALUES (5003, 'MARKETING', 'Honolulu', 9);
1 row inserted.

iSQL> INSERT INTO departments VALUES (5004, 'PLANNING', 'Washington DC', 15);
1 row inserted.

iSQL> INSERT INTO departments VALUES (5005, 'OPERATIONS', 'Budapest', 2);
1 row inserted.
```

Remote Data Download

Local server

```
$ iloader formout -s 192.168.1.10 -u sys -p manager -port 21300 -T depart-
ments -f dept.fmt
```

```
-----
Altibase Data Load/Download utility.
Release Version 6.1.1.1
Copyright 2000, ALTIBASE Corporation or its subsidiaries.
All Rights Reserved.
-----
```

```
ISQL_CONNECTION : TCP
```

```
$ ls
dept.fmt
```

```
$ iloader out -s 192.168.1.10 -u sys -p manager -port 21300 -f dept.fmt -d
dept.dat
```

```
-----
Altibase Data Load/Download utility.
Release Version 6.1.1.1
Copyright 2000, ALTIBASE Corporation or its subsidiaries.
All Rights Reserved.
-----
```

```
ISQL_CONNECTION : TCP
DATA_NLS_USE: K016KSC5601
NCHAR_UTF16 : YES
```

```
Total 5 record downloaded(departments)
```

2.4 Using iLoader in Batch Mode

```
DOWNLOAD: 1.1490 msec
```

```
$ ls
dept.dat dept.fmt
```

Remote Data Upload

Local server

```
$ iloader in -s 192.168.1.10 -u sys -p manager -port 21300 -f dept.fmt -d
dept.dat -mode replace
```

```
-----
Altibase Data Load/Download utility.
Release Version 6.1.1.1
Copyright 2000, ALTIBASE Corporation or its subsidiaries.
All Rights Reserved.
-----
```

```
ISQL_CONNECTION : TCP
DATA_NLS_USE: KO16KSC5601
NCHAR_UTF16 : YES
```

```
UPLOAD : 26.0640 msec
```

```
Load Count : 5(departments)
```

Result

Remote server (192.168.1.10)

```
iSQL> SELECT * FROM departments;
```

DNO	DNAME	DEP_LOCATION	MGR_NO
5001	TECHNICAL	Las Vegas	1
5002	ENGINE DEVT	Munich	10
5003	MARKETING	Honolulu	9
5004	PLANNING	Washington DC	15
5005	OPERATIONS	Budapest	9

```
5 rows selected.
```

2.5 Using iLoader in Interactive Mode

If you don't enter any of the mandatory inputs for iLoader execution, i.e. formout / out / in, the iLoader> prompt will be displayed, and iLoader will be executed in interactive mode. In interactive mode, command-line options can be used the same way as in batch mode.

2.5.1 Starting iLoader

You must first be logged in before entering interactive mode. Connection information can be entered either on the command line or via iLoader. Additional information required to establish a connection with the server includes the server name (-S), user name (-U) and password (-P). The password is not case-sensitive, but the user name is if you use double quotation marks to enclose this.

2.5.1.1 How to Enter Connection Information on the Command line

```
$ iloader -s 127.0.0.1 -u sys -p manager
-----
Altibase Data Load/Download utility.
Release Version 6.1.1.1
Copyright 2000, ALTIBASE Corporation or its subsidiaries.
All Rights Reserved.
-----
ISQL_CONNECTION : TCP
iLoader> -> When the iLoader prompt appears, enter a command to accomplish a desired task in interactive mode.
```

2.5.1.2 How to Enter Connection Information in iLoader

```
$ iloader
-----
Altibase Data Load/Download utility.
Release Version 6.1.1.1
Copyright 2000, ALTIBASE Corporation or its subsidiaries.
All Rights Reserved.
-----
Write Server Name (enter:127.0.0.1) :
Write UserID : sys
Write Password : -> The password is not output to the screen.
ISQL_CONNECTION : TCP
iLoader> -> When the iLoader prompt appears, enter a command to accomplish a desired task in interactive mode.
```

2.5.1.3 Exiting Interactive Mode

```
iLoader> exit
```

2.5.2 Creating FORM Files

```
iLoader> formout -T employees -f employees.fmt
iLoader> exit
$ ls
```

2.5 Using iLoader in Interactive Mode

```
employees.fmt
```

2.5.3 Downloading Data

```
iLoader> out -f employees.fmt -d employees.dat  
DATE_FORMAT : YYYY/MM/DD HH:MI:SS:SSSSSS  
DATA_NLS_USE : KO16KSC5601  
NCHAR_UTF16 : YES
```

```
Total 20 record download(EMPLOYEES)
```

```
DOWNLOAD : 54.7250 msec
```

```
iLoader> exit
```

```
$ ls  
employees.dat employees.fmt
```

2.5.4 Uploading Data

```
iLoader> in -f employees.fmt -d employees.dat -mode replace  
DATE_FORMAT : YYYY/MM/DD HH:MI:SS:SSSSSS  
DATA_NLS_USE : KO16KSC5601  
NCHAR_UTF16 : YES
```

```
UPLOAD : 9.4580 msec
```

```
Load Count : 20(EMPLOYEES)
```

2.5.5 Execution Result Code

ALTIBASE HDB displays one of the following execution result codes after downloading or uploading data using iLoader.

- 0 : Success
- -1 : General Error
- -2 : One or more upload errors have occurred.

0 or -1 is displayed to indicate success or failure, respectively, of a data upload or download operation. -2 is displayed to indicate that the overall upload operation succeeded but that one or more errors occurred.

2.5.6 Remote Access in Interactive Mode

When iLoader is executed remotely, if none of the command-line options (formout / out / in) are entered, and only the port number is entered, the user will be prompted to enter the option values.

If access is successful, an iLoader prompt will appear, and a command can be entered to perform a desired task interactively.

In the following example, after the port number of a remote server is used to access the remote server from a local server, the iLoader utility is used to download the data from the MANAGER table

on the remote server to a file, and then to upload the data back to the MANAGER table.

- Remote server (IP 192.168.1.10, PORT_NO: 21300)
- Communication protocol :TCP/IP (ISQL_CONNECTION=TCP/IP)

2.5.6.1 Remote Server Data

Remote server (192.168.1.10)

```
iSQL> CREATE TABLE manager(
mgr_no INTEGER,
mname VARCHAR(20),
address VARCHAR(60));
Create success.

iSQL> INSERT INTO manager VALUES (7, 'HJMIN', '44-25 Youido-dong Youngdungpo-
gu Seoul, Korea');
1 row inserted.

iSQL> INSERT INTO manager VALUES(8, 'JDLEE', '3101 N. Wabash Ave. Brooklyn,
NY');
1 row inserted.

iSQL> INSERT INTO manager VALUES(12, 'MYLEE', '130 Gongpyeongno Jung-gu
Daegu, Korea');
1 row inserted.

iSQL> SELECT * FROM manager;
MGR_NO      MNAME      ADDRESS
-----
7           HJMIN      44-25 Youido-dong Youngdungpo-gu Seoul, Korea
8           JDLEE      3101 N. Wabash Ave. Brooklyn, NY
12          MYLEE      130 Gongpyeongno Jung-gu Daegu, Korea
3 rows selected.
```

2.5.6.2 Remote Data Download and Upload

Local server

```
$ iloader -s 192.168.1.10 -u sys -p manager -port 21300
-----
Altibase Data Load/Download utility.
Release Version 6.1.1.1
Copyright 2000, ALTIBASE Corporation or its subsidiaries.
All Rights Reserved.
-----
ISQL_CONNECTION : TCP
iLoader> ->iLoader is connected to the server, and in this mode commands can be entered to interactively
perform a desired task.
```

or

```
$ iloader -port 21300
-----
Altibase Data Load/Download utility.
Release Version 6.1.1.1
Copyright 2000, ALTIBASE Corporation or its subsidiaries.
All Rights Reserved.
-----
```


2.5 Using iLoader in Interactive Mode

```
Write Server Name (enter:127.0.0.1) : 192.168.1.10
Write UserID : sys
Write Password : ->The password is not displayed on the screen.
ISQL_CONNECTION : TCP
```

```
iLoader> formout -T MANAGER -f MANAGER.fmt
```

```
iLoader> out -f MANAGER.fmt -d MANAGER.dat
DATA_NLS_USE: KO16KSC5601
NCHAR_UTF16 : YES
```

```
Total 3 record download(MANAGER)
```

```
DOWNLOAD : 1.3110 msec
```

```
iLoader> in -f MANAGER.fmt -d MANAGER.dat
DATA_NLS_USE: KO16KSC5601
NCHAR_UTF16 : YES
```

```
UPLOAD : 30.4730 msec
```

```
Load Count : 3 (MANAGER)
```

2.5.6.3 Result

Remote server (192.168.1.10)

```
iSQL> SELECT * FROM manager;
MGR_NO  MNAME  ADRESS
```

```
-----
7       HJMIN   44-25 Youido-dong Youngdungpo-gu Seoul, Korea
8       JDLEE   3101 N. Wabash Ave. Brooklyn, NY
12      MYLEE   130 Gongpyeongno Jung-gu Daegu, Korea
7       HJMIN   44-25 Youido-dong Youngdungpo-gu Seoul, Korea
8       JDLEE   3101 N. Wabash Ave. Brooklyn, NY
12      MYLEE   130 Gongpyeongno Jung-gu Daegu, Korea
6 rows selected. ->The data have been appended to the table MANAGER.
```

2.6 Online Help and Other Options

2.6.1 Help

Help is available for the commands provided with iLoader. The HELP command displays all help information. For help on a specific command, enter the HELP command followed by the information for which help is needed.

2.6.1.1 Example

```
iLoader> help
Usage : { in | out | formout | structout | help }
        [-d datafile or datafiles] [-f formatfile]
        [-T table_name] [-F firstrow] [-L lastrow]
        [-t field_term] [-r row_term] [-mode mode_type]
        [-commit commit_unit] [-bad badfile]
        [-log logfile] [-e enclosing] [-array count]
        [-replication true/false] [-split number]
        [-readsize size] [-errors count]
        [-lob lob_option_string] [-atomic]
        [-parallel count] [-direct]
        [-rule csv]

iLoader> help help
Ex) help [ in | out | formout | structout | exit | help ]

iLoader> help in
Ex) in -f $formatfile -d $datafile -bad $badfile -log $logfile -e $enclosing

iLoader> help out
Ex) out -f $formatfile -d $datafile -split $number

iLoader> help exit
Ex> exit (or quit)
```

or

```
$ iloader help
=====
                          ILOADER HELP Screen
=====
Usage   : iloader [-h]
          [-s server_name] [-u user_name] [-p password]
          [-port port_no] [-silent] [-nst] [-displayquery]
          [-NLS_USE nls_name]
          [-prefer_ipv6]
          [{ in | out | formout | structout | help }
          [-d datafile or datafiles] [-f formatfile]
          [-T table_name] [-F firstrow] [-L lastrow]
          [-t field_term] [-r row_term] [-mode mode_type]
          [-commit commit_unit] [-bad badfile]
          [-log logfile] [-e enclosing] [-array count]
          [-replication true/false] [-split number]
          [-readsize size] [-errors count]
          [-lob lob_option_string] [-atomic]
          [-parallel count] [-direct]
          [-rule csv]]

          -h           : This screen
```

2.6 Online Help and Other Options

```
-s          : Specify server name to connect
-u          : Specify user name to connect
-p          : Specify password of specify user name
-port      : Specify port number to communication
-silent    : No display Copyright
-nst       : No display Elapsed Time
-displayquery : display query string
-NLS_USE   : Specify NLS
-prefer_ipv6 : Prefer resolving server_name to IPv6 Address
=====
```

2.6.2 Other Options

- -log iLoader records task results, execution progress and errors that occurred during execution.
- -bad rows that could not be uploaded due to the occurrence of errors during loading are recorded.

2.6.2.1 Example

```
$ isql -s localhost -u sys -p manager -silent
iSQL> CREATE TABLE test1 (i1 INTEGER);
Create success.
iSQL> CREATE TABLE test2 (c1 CHAR(1));
Create success.
iSQL> INSERT INTO test2 VALUES(1);
1 row inserted.
iSQL> INSERT INTO test2 VALUES('A');
1 row inserted.
iSQL> INSERT INTO test2 VALUES(2);
1 row inserted.
iSQL> exit

$ iloader -s localhost -u sys -p manager -silent
iLoader> formout -T test1 -f test1.fmt

iLoader> formout -T test2 -f test2.fmt

iLoader> out -f test2.fmt -d test2.dat
DATA_NLS_USE: KO16KSC5601
NCHAR_UTF16 : YES

Total 3 record download(TEST2)

DOWNLOAD : 1.0420 msec

iLoader> in -f test1.fmt -d test2.dat -log test.log -bad test.bad
DATA_NLS_USE: KO16KSC5601
NCHAR_UTF16 : YES

UPLOAD : 6.6670 msec

Load Count : 2(TEST1)
Error Count : 1

iLoader> exit

$ cat test.bad
A
```

```
$ cat test.log
<DataLoad>
TableName : TEST1
Start Time : Thu Sep 30 10:39:46 2010
Record 2 : A
[ERR-21011 : Invalid literal]
End Time : Thu Sep 30 10:39:46 2010
Total Row Count : 3
Load Row Count  : 2
Error Row Count : 1
```

2.6 Online Help and Other Options

3 FORM Files

3.1 About FORM Files

A FORM file is similar to a Create Table statement in that contains information for iLoader about the attributes of a table with which data are to be exchanged. iLoader can be used to automatically create FORM files. They can also be directly edited to use the following three additional options.

- `SEQUENCE sequence_name column_name [NEXTVAL | CURRVAL]`
- `DATEFORM date_format`
- `DOWNLOAD CONDITION "WHERE condition"`

3.1.1 Writing SEQUENCE Statements

A FORM file can be modified to implement a SEQUENCE.

To modify the FORM file, enter the word SEQUENCE followed by the sequence name, the name of the column(s) to be used, and pseudocolumns such as NEXTVAL or CURRVAL, etc in order at the very beginning of the form file.

```
SEQUENCE sequence_name column_name [ NEXTVAL | CURRVAL ]
```

The default value for pseudocolumns is NEXTVAL.

The maximum number of columns that can be used is 8

The default format of the FORM file is as follows, and if the table has a column for which the data type is date, the date format will be the default.

```
Ex) table sample
{
A numeric (10);
B numeric (10, 4);
C char (10);
D varchar (10);
E date;
}
DATEFORM YYYY/MM/DD HH:MI:SS:SSSSSS
```

3.1.1.1 Example

```
iSQL> CREATE TABLE seqTable(
  num INTEGER,
  name VARCHAR(30));
Create success.
iSQL> INSERT INTO seqTable VALUES(1, 'JANE');
1 row inserted.
iSQL> INSERT INTO seqTable VALUES(2, 'SARA');
1 row inserted.

iSQL> CREATE SEQUENCE seq1
  START WITH 30 INCREMENT BY 2
  MINVALUE 0 NOMAXVALUE;
Create success.

iLoader> formout -T seqTable -f seqTable.fmt
```

```

$ vi seqTable.fmt
SEQUENCE seq1 NUM -> Revised part
table SEQTABLE
{
"NUM" integer;
"NAME" varchar (30);
}
DATA_NLS_USE=US7ASCII

iSQL> INSERT INTO seqTable(name) VALUES ('JOHN');
1 row inserted.
iSQL> INSERT INTO seqTable(name) VALUES ('JOHNSON');
1 row inserted.
iSQL> SELECT * FROM seqTable;
NUM          NAME
-----
1            JANE
2            SARA
             JOHN
             JOHNSON
4 rows selected.

```

After using the FORM file to back up seqTable table to a file, when the file is examined it looks like;

```

iLoader> out -f seqTable.fmt -d seqTable.dat
DATA_NLS_USE: US7ASCII

```

```

    Total 4 record download(SEQTABLE)

```

```

    DOWNLOAD : 53.4390 msec

```

```

$ cat seqTable.dat
1, "JANE"
2, "SARA"
, "JOHN"
, "JOHNSON"

```

After uploading the backup file to the current database, the following statement is used:

```

iLoader> in -f seqTable.fmt -d seqTable.dat -mode replace
DATA_NLS_USE: US7ASCII

```

```

    UPLOAD : 8.9460 msec

```

```

    Load Count : 4 (SEQTABLE)

```

If the records in the seqTable table are queried, the results will be as follows:

```

iSQL> SELECT * FROM seqTable;
NUM          NAME
-----
30            JANE
32            SARA
34            JOHN
36            JOHNSON
4 rows selected.

```

3.1.2 Modifying Date Format Strings in a FORM File

The format for date data type columns can be set as follows (case-insensitive), and download or upload actions can be conducted on the basis of the format.

3.1 About FORM Files

The date format should be specified at the bottom of the FORM file when modifying it. The default is DATEFORM YYYY/MM/DD HH:MI:SS:SSSSSS.

```
DATEFORM YYYY-MM-DD HH:MI:SS:SSSSSS
DATEFORM YYYY/MM/DD HH:MI:SS:SSSSSS
DATEFORM YY/MM/DD HH:MI:SS:SSSSSS
DATEFORM YY-MM-DD HH:MI:SS:SSSSSS
DATEFORM YYYYMMDDHHMISSSSSSSSS
DATEFORM YYMMDDHHMISSSSSSSSS
DATEFORM YY
DATEFORM YYYY
DATEFORM YYMMDD
DATEFORM YYYYMMDD
DATEFORM HHMISSSSSSS
DATEFORM HH:MI:SS:SSSS
DATEFORM HH:MI:SS
```

Single quotation marks (' and ') can be used to define a new date format that differs from the date formats given above.

For example, a date format that uses a space as the delimiter between the year, month and day elements can be defined thus: "DATEFORM YY MM DD" or "DATEFORM YYYY MM DD".

```
iSQL> CREATE TABLE t1(
  i1 INTEGER,
  i2 DATE,
  i3 INTEGER);
Create success.
iSQL> INSERT INTO t1 VALUES(1, TO_DATE('2002-01-23 10:11:12:222222', 'YYYY-
MM-DD HH:MI:SS:SSSSSS'), 1);
1 row inserted.
iSQL> INSERT INTO t1 VALUES(2, TO_DATE('2002-01-23 13:14:15:333333', 'YYYY-
MM-DD HH:MI:SS:SSSSSS'), 2);
1 row inserted.
iSQL> INSERT INTO t1 VALUES(3, TO_DATE('2002-01-23 16:17:18:444444', 'YYYY-
MM-DD HH:MI:SS:SSSSSS'), 3);
1 row inserted.

iSQL> SELECT TO_CHAR(i2, 'YYYY-MM-DD HH:MI:SS:SSSSSS') testdate FROM t1;
TESTDATE
-----
2002-01-23 10:11:12:222222
2002-01-23 13:14:15:333333
2002-01-23 16:17:18:444444
3 rows selected.
```

The created FORM file is modified as follows:

```
iLoader> formout -T t1 -f t1.fmt

$ vi t1.fmt
table T1
{
  "I1" integer;
  "I2" date;
  "I3" integer;
}
DATEFORM YYYY-MM-DD HH:MI:SS:SSSSSS -> Revised part
DATA_NLS_USE=US7ASCII
```

After the FORM file is used to back up the seqTable table to a file, examining the file reveals the following,

```
iLoader> out -f t1.fmt -d t1.dat
DATE FORMAT : YYYY-MM-DD HH:MI:SS:SSSSSS
DATA_NLS_USE: US7ASCII
```

```
Total 3 record download(T1)
```

```
DOWNLOAD : 982.0000 usec
```

```
$ cat t1.dat
1,"2002-01-23 10:11:12:222222",1
2,"2002-01-23 13:14:15:333333",2
3,"2002-01-23 16:17:18:444444",3
```

To upload the backup file to the database, the following command is used.

```
iLoader> in -f t1.fmt -d t1.dat -mode replace
DATE FORMAT : YYYY-MM-DD HH:MI:SS:SSSSSS
DATA_NLS_USE: US7ASCII
```

```
UPLOAD : 10.0930 msec
```

```
Load Count : 3(T1)
```

Selecting the records in table t1 using the TO_CHAR function results in the following:

```
iSQL> SELECT TO_CHAR(i2, 'YYYY-MM-DD HH:MI:SS:SSSSSS') TESTDATE FROM t1;
TESTDATE
-----
2002-01-23 10:11:12:222222
2002-01-23 13:14:15:333333
2002-01-23 16:17:18:444444
3 rows selected.
```

However, when uploading data, it is important to ensure that the previously downloaded data have the same date format specified in the FORM file.

3.1.2.1 DATE FORMAT Environment Variable

In the FORM file structure, an environment variable that plays a role analogous to that of DATEFORM can be specified as follows. For example, when using the Bourne, Korn, or Bash Shells

```
$ export ILO_DATEFORM='YYYY-MM-DD'
```

3.1.2.2 How to specify the DATE FORMAT for Respective Columns

When dealing with DATE data type columns that have different formats, if the FORM file is modified by entering DATEFORM and a desired date_format in double quotes (" ") after the DATE type declaration (not case sensitive), data can be uploaded or downloaded in this format.

```
iSQL> CREATE TABLE t1 (i1 INTEGER, i2 DATE, i3 DATE, i4 DATE);
Create success.
```

```
iSQL> INSERT INTO t1 VALUES (1,
TO_DATE('2004/11/24 09:55:30 181133', 'YYYY/MM/DD HH:MI:SS SSSSSS'),
TO_DATE('2004/11/25 09:55:30 181133', 'YYYY/MM/DD HH:MI:SS SSSSSS'),
TO_DATE('2004/11/26 09:55:30 181133', 'YYYY/MM/DD HH:MI:SS SSSSSS'));
1 row inserted.
```

3.1 About FORM Files

```
iSQL> SELECT * FROM t1;
I1          I2          I3          I4
-----
1          24-NOV-2004  25-NOV-2004  26-NOV-2004
1 row selected.

$ iloader formout -s 127.0.0.1 -u sys -p manager -T t1 -f t1.fmt;

$ vi t1.fmt
table T1
{
"I1" integer;
"I2" date DATEFORM "YYYY-MM-DD"; -> Revised part
"I3" date;
"I4" date DATEFORM "YYYY/MM/DD HH:MI:SS SSSSSS"; -> Revised part
}
DATEFORM YYYY/MM/DD HH:MI:SS:SSSSSS
DATA_NLS_USE=US7ASCII

$ iloader out -s 127.0.0.1 -u sys -p manager -f t1.fmt -d t1.dat;
DATE FORMAT : YYYY/MM/DD HH:MI:SS:SSSSSS
DATA_NLS_USE: US7ASCII

      Total 1 record download(T1)

      DOWNLOAD : 1.0710 msec

$ cat t1.dat
1,"2004-11-24","2004/11/25 09:55:30","2004/11/26 09:55:30 181133"

$ iloader in -s 127.0.0.1 -u sys -p manager -f t1.fmt -d t1.dat;
DATE FORMAT : YYYY/MM/DD HH:MI:SS:SSSSSS
DATA_NLS_USE: US7ASCII

      UPLOAD : 13.7350 msec

      Load Count : 1(T1)

iSQL> SELECT * FROM t1;
I1          I2          I3          I4
-----
1          24-NOV-2004  25-NOV-2004  26-NOV-2004
1          24-NOV-2004  25-NOV-2004  26-NOV-2004
2 rows selected.

iSQL> SELECT TO_CHAR(I2,'YYYY/MM/DD HH:MI:SS SSSSSS') FROM t1;
TO_CHAR(I2,'YYYY/MM/DD HH:MI:SS SSSSSS')
-----
2004/11/24 09:55:30 181133
2004/11/24 00:00:00 000000
2 rows selected.

iSQL> SELECT TO_CHAR(I3,'YYYY/MM/DD HH:MI:SS SSSSSS') FROM t1;
TO_CHAR(I3,'YYYY/MM/DD HH:MI:SS SSSSSS')
-----
2004/11/25 09:55:30 181133
2004/11/25 09:55:30 000000
2 rows selected.

$ SELECT TO_CHAR(I4,'YYYY/MM/DD HH:MI:SS SSSSSS') FROM t1;
TO_CHAR(I4,'YYYY/MM/DD HH:MI:SS SSSSSS')
-----
2004/11/26 09:55:30 181133
```

```
2004/11/26 09:55:30 181133
2 rows selected.
```

Note:

The date format specifications take precedence in the following order (from highest precedence to lowest):

- 1) the specification following the DATE column in the FORM file
- 2) the ILO_DATEFORM environment variable
- 3) 'DATEFORM YYYY/MM/DD HH:MI:SS:SSSSSS' in the FORM file

3.1.2.3 Executing Functions

Data being uploaded can be placed in a particular column using a function. However, this is not possible for the data types DATE, TIMESTAMP or GEOMETRY.

When modifying a FORM file, the function name should be specified in double quotes (" ") after the other options. Furthermore, a question mark (?) should be used to indicate the location at which the column is to be bound.

```
$ vi t2.fmt
table t2
{
"I1" integer "trim(?)"; -> Revised part
"I2" varchar(10) "trim(?)"; -> Revised part
"I3" varchar(10) "concat(trim(?), 'value')"; -> Revised part
}
```

3.1.3 Writing Condition Clauses

FORM files can be modified so that condition clauses are used when downloading data from tables. Hints can also be added to realize improved performance.

Enter the words "DOWNLOAD CONDITION" (without quotes) at the very end of a FORM file, followed by the condition clause within double quotes (" "). At the time of execution, the executed query can be checked to verify that hints and condition clauses specified by the user are working properly using the "-displayquery" option.

3.1.3.1 Syntax

```
DOWNLOAD CONDITION "WHERE conditions_clause"
[HINT "hint_string"]
```

conditions_clause : For specifying conditions. Has the same form as the WHERE clause of a SELECT statement.

hint_name : For specifying a hint in order to increase the performance of a SELECT statement. Has the same form as a HINT used with a SELECT statement.

3.1.3.2 Example

```
iSQL> CREATE TABLE table1(
t1 INTEGER,
t2 INTEGER,
t3 DATE);
```

3.1 About FORM Files

```
Create success.
iSQL> INSERT INTO table1 VALUES(1, 1, '01-May-2002');
1 row inserted.
iSQL> INSERT INTO table1 VALUES(2, 2, '02-Jun-2002');
1 row inserted.
iSQL> INSERT INTO table1 VALUES(3, 3, '03-Apr-2002');
1 row inserted.
iSQL> INSERT INTO table1 VALUES(4, 4, '04-Sep-2002');
1 row inserted.
iSQL> INSERT INTO table1 VALUES(5, 5, '05-Oct-2002');
1 row inserted.
iSQL> SELECT * FROM table1;
T1          T2          T3
-----
1           1           01-MAY-2002
2           2           02-JUN-2002
3           3           03-APR-2002
4           4           04-SEP-2002
5           5           05-OCT-2002
5 rows selected.
```

The FORM file created with this command:

```
iLoader> formout -T table1 -f table1.fmt
```

is modified as follows:

```
$ vi table1.fmt
table TABLE1
{
"T1" integer;
"T2" integer;
"T3" date;
}
DATEFORM YYYY/MM/DD HH:MI:SS:SSSSSS
DATA-NLS_USE=US7ASCII
DOWNLOAD CONDITION "WHERE t1 > 2" -> Revised Part
```

After using the FORM file to back up table1 to a file, when the file is examined, the results of application of the condition clause can be seen.

```
iLoader> out -f table1.fmt -d table1.dat
DATE FORMAT : YYYY/MM/DD HH:MI:SS:SSSSSS
DATA-NLS_USE: US7ASCII
```

```
Total 3 record download(TABLE1)
```

```
DOWNLOAD : 1.4150 msec
```

```
$ cat table1.dat
3,3,"2002/04/03 00:00:00"
4,4,"2002/09/04 00:00:00"
5,5,"2002/10/05 00:00:00"
```

3.1.4 Handling TIMESTAMP Columns

After downloading a data file from a current Altibase database using iLoader, a value pertaining to a TIMESTAMP column in a data file can be uploaded by using the following options to modify the FORM file.

- ADD DEFAULT

- ADD NULL
- ADD YYYYMMDD[HHMISS]
- SKIP DEFAULT
- SKIP NULL
- SKIP YYYYMMDD[HHMISS]

Below is an example of the use of the above option to download the data in a database table to a file and upload the data to the table again.

1. A FORM file is created based on the table to be downloaded from the current Altibase database.
2. The created FORM file is used to back up the table data, downloaded from the current database, to a file.
3. The FORM file to be uploaded is modified according to the following guidelines as the circumstances require.

3.1.4.1 If the data file has no value in a **TIMESTAMP** column

- If there are no **TIMESTAMP** data in the data file, but the current time is to be entered in the **TIMESTAMP** column: enter "ADD DEFAULT" (without quotation marks) at the end of the line describing the **TIMESTAMP** column in the FORM file to be uploaded (or delete the line describing the **TIMESTAMP** column from the FORM file).
- If there are no **TIMESTAMP** data in the data file, and a null value is to be entered in the **TIMESTAMP** column: enter "ADD NULL" at the end of the line describing the **TIMESTAMP** column in the FORM file to be used for uploading data.
- If there are no **TIMESTAMP** data in the data file, but a specified value is to be entered in the **TIMESTAMP** column: enter "ADD YYYYMMDD[HHMISS]" at the end of the line describing the **TIMESTAMP** column in the FORM file to be used for uploading data.

```
Ex) YYYYMMDD [HHMISS]
ADD 20040623
ADD 20040623102315
```

3.1.4.2 If a value corresponding to a **TIMESTAMP** column is in the data file

- To discard the value in the data file and enter the current time instead: enter "SKIP DEFAULT" at the end of the **TIMESTAMP** column of the FORM file to be uploaded.
- To enter NULL instead of the value in the data file: enter "SKIP NULL" at the end of the **TIMESTAMP** column of the FORM file to be uploaded.
- To enter a specified value instead of the value in the data file: enter "ADD YYYYMMDD [HHMISS]" at the end of the **TIMESTAMP** column of the FORM file to be uploaded.

Use the edited FORM file to upload data to the current database.

3.1 About FORM Files

3.1.4.3 Example

ADD DEFAULT

```
iSQL> CREATE TABLE test (i1 INTEGER);
Create success.

iSQL> CREATE TABLE test2 (
  i1 INTEGER,
  i2 TIMESTAMP
);
Create success.

iSQL> INSERT INTO test VALUES(1);
1 row inserted.

iSQL> INSERT INTO test VALUES(2);
1 row inserted.

iSQL> INSERT INTO test VALUES(3);
1 row inserted.

$ iloader formout -s 127.0.0.1 -u sys -p manager -T TEST -f test.fmt;

$ iloader out -s 127.0.0.1 -u sys -p manager -f test.fmt -d test.dat;
DATA_NLS_USE: US7ASCII

      Total 3 record download(TEST)

      DOWNLOAD : 831.0000 usec

$ cat test.dat
1
2
3

$ iloader formout -s 127.0.0.1 -u sys -p manager -T test2 -f t2_add_default.fmt;

$ vi t2_add_default.fmt
table TEST2
{
  "I1" integer;
  "I2" timestamp ADD DEFAULT; -> Revised part
}
DATEFORM YYYY/MM/DD HH:MI:SS:SSSSSS
DATA_NLS_USE=US7ASCII

$ iloader in -s 127.0.0.1 -u sys -p manager -f t2_add_default.fmt -d
test.dat;
DATE FORMAT : YYYY/MM/DD HH:MI:SS:SSSSSS
DATA_NLS_USE: US7ASCII

UPLOAD : 12.2470 msec

      Load Count : 3(TEST2)

iSQL> SELECT * FROM test2;
I1          I2
-----
1          4CA92B4500074CAB
2          4CA92B4500074CF8
3          4CA92B4500074D27
3 rows selected.
```

ADD NULL

```

iSQL> CREATE TABLE test (i1 INTEGER);
Create success.

iSQL> CREATE TABLE test2 (
  i1 INTEGER,
  i2 TIMESTAMP
);
Create success.

iSQL> INSERT INTO test VALUES(1);
1 row inserted.

iSQL> INSERT INTO test VALUES(2);
1 row inserted.

iSQL> INSERT INTO test VALUES(3);
1 row inserted.

$ iloader formout -s 127.0.0.1 -u sys -p manager -T TEST -f test.fmt;

$ iloader out -s 127.0.0.1 -u sys -p manager -f test.fmt -d test.dat;
DATA-NLS_USE: US7ASCII

      Total 3 record download(TEST)

      DOWNLOAD : 833.0000 usec

$ cat test.dat
1
2
3

$ iloader formout -s 127.0.0.1 -u sys -p manager -T TEST2 -f t2_add_null.fmt;

$ vi t2_add_null.fmt
table TEST2
{
  "I1" integer;
  "I2" timestamp ADD NULL; -> Revised part
}
DATEFORM YYYY/MM/DD HH:MI:SS:SSSSSS
DATA-NLS_USE=US7ASCII

$ iloader in -s 127.0.0.1 -u sys -p manager -f t2_add_null.fmt -d test.dat;
DATE FORMAT : YYYY/MM/DD HH:MI:SS:SSSSSS
DATA-NLS_USE: US7ASCII

UPLOAD : 11.2610 msec

      Load Count   : 3(TEST2)

iSQL> SELECT * FROM test2;
I1          I2
-----
1
2
3
3 rows selected.

```


3.1 About FORM Files

ADD YYYYMMDD [HHMISS]

```
iSQL> CREATE TABLE test (i1 INTEGER);
Create success.

iSQL> CREATE TABLE test2 (
  i1 INTEGER,
  i2 TIMESTAMP
);
Create success.

iSQL> INSERT INTO test VALUES(1);
1 row inserted.

iSQL> INSERT INTO test VALUES(2);
1 row inserted.

iSQL> INSERT INTO test VALUES(3);
1 row inserted.

$ iloader formout -s 127.0.0.1 -u sys -p manager -T TEST -f test.fmt;

$ iloader out -s 127.0.0.1 -u sys -p manager -f test.fmt -d test.dat;
DATA-NLS_USE: US7ASCII

      Total 3 record download(TEST)

      DOWNLOAD : 801.0000 usec

$ cat test.dat
1
2
3

$ iloader formout -s 127.0.0.1 -u sys -p manager -T TEST2 -f t2_add_val.fmt;

$ vi t2_add_val.fmt
table TEST2
{
  "I1" integer;
  "I2" timestamp ADD 20040623; -> Revised Part
}
DATEFORM YYYY/MM/DD HH:MI:SS:SSSSSS
DATA-NLS_USE=US7ASCII

$ iloader in -s 127.0.0.1 -u sys -p manager -f t2_add_val.fmt -d test.dat;
DATE FORMAT : YYYY/MM/DD HH:MI:SS:SSSSSS
DATA-NLS_USE: US7ASCII

UPLOAD : 9.9950 msec

      Load Count : 3(TEST2)

iSQL> SELECT * FROM test2;
I1          I2
-----
1          40D8497000000000
2          40D8497000000000
3          40D8497000000000
3 rows selected.
```

SKIP DEFAULT

```

iSQL> CREATE TABLE test (
  i1 INTEGER,
  i2 TIMESTAMP
);
Create success.

iSQL> CREATE TABLE test2 (
  i1 INTEGER,
  i2 TIMESTAMP
);
Create success.

iSQL> INSERT INTO test VALUES(1, BYTE'40D930BF000A7566');
1 row inserted.

iSQL> INSERT INTO test VALUES(2, BYTE'40D930BF000A7566');
1 row inserted.

iSQL> INSERT INTO test VALUES(3, BYTE'40D930BF000A7566');
1 row inserted.

$ iloader formout -s 127.0.0.1 -u sys -p manager -T TEST -f test.fmt;

$ iloader out -s 127.0.0.1 -u sys -p manager -f test.fmt -d test.dat;
DATE FORMAT : YYYY/MM/DD HH:MI:SS:SSSSSS
DATA_NLS_USE: US7ASCII

      Total 3 record download(TEST)

      DOWNLOAD : 859.0000 usec

$ cat test.dat
1,40D930BF000A7566
2,40D930BF000A7566
3,40D930BF000A7566

$ iloader formout -s 127.0.0.1 -u sys -p manager -T test2 -f
t2_skip_default.fmt;

$ vi t2_skip_default.fmt
table TEST2
{
  "I1" integer;
  "I2" timestamp SKIP DEFAULT; -> Revised Part
}
DATEFORM YYYY/MM/DD HH:MI:SS:SSSSSS
DATA_NLS_USE=US7ASCII

$ iloader in -s 127.0.0.1 -u sys -p manager -f t2_skip_default.fmt -d
test.dat;

DATE FORMAT : YYYY/MM/DD HH:MI:SS:SSSSSS
DATA_NLS_USE: US7ASCII

UPLOAD : 7.4390 msec

      Load Count   : 3(TEST2)

iSQL> SELECT * FROM test2;
I1          I2
-----
1           4CA92F9F000759E2

```

3.1 About FORM Files

```
2          4CA92F9F00075A2E
3          4CA92F9F00075A5F
3 rows selected.
```

SKIP NULL

```
iSQL> CREATE TABLE test (
  i1 INTEGER,
  i2 TIMESTAMP
);
Create success.

iSQL> CREATE TABLE test2 (
  i1 INTEGER,
  i2 TIMESTAMP
);
Create success.

iSQL> INSERT INTO test VALUES(1, BYTE'40D930BF000A7566');
1 row inserted.

iSQL> INSERT INTO test VALUES(2, BYTE'40D930BF000A7566');
1 row inserted.

iSQL> INSERT INTO test VALUES(3, BYTE'40D930BF000A7566');
1 row inserted.

$ iloader formout -s 127.0.0.1 -u sys -p manager -T TEST -f test.fmt;

$ iloader out -s 127.0.0.1 -u sys -p manager -f test.fmt -d test.dat;
DATE FORMAT : YYYY/MM/DD HH:MI:SS:SSSSSS
DATA_NLS_USE: US7ASCII

      Total 3 record download(TEST)

      DOWNLOAD : 856.0000 usec

$ cat test.dat
1,40D930BF000A7566
2,40D930BF000A7566
3,40D930BF000A7566

$ iloader formout -s 127.0.0.1 -u sys -p manager -T TEST2 -f t2_skip_null.fmt;

$ vi t2_skip_null.fmt
table TEST2
{
  "I1" integer;
  "I2" timestamp SKIP NULL; -> Revised part
}
DATEFORM YYYY/MM/DD HH:MI:SS:SSSSSS
DATA_NLS_USE=US7ASCII

$ iloader in -s 127.0.0.1 -u sys -p manager -f t2_skip_null.fmt -d test.dat;
DATE FORMAT : YYYY/MM/DD HH:MI:SS:SSSSSS
DATA_NLS_USE: US7ASCII

UPLOAD : 5.3590 msec

      Load Count   : 3(TEST2)

iSQL> SELECT * FROM test2;
I1          I2
-----
```

```

1
2
3
3 rows selected.

```

SKIP YYYYMMDD [HHMISS]

```

iSQL> CREATE TABLE test (
  i1 INTEGER,
  i2 TIMESTAMP
);
Create success.

iSQL> CREATE TABLE test2 (
  i1 INTEGER,
  i2 TIMESTAMP
);
Create success.

iSQL> INSERT INTO test VALUES(1, BYTE'40D930BF000A7566');
1 row inserted.

iSQL> INSERT INTO test VALUES(2, BYTE'40D930BF000A7566');
1 row inserted.

iSQL> INSERT INTO test VALUES(3, BYTE'40D930BF000A7566');
1 row inserted.

$ iloader formout -s 127.0.0.1 -u sys -p manager -T TEST -f test.fmt;

$ iloader out -s 127.0.0.1 -u sys -p manager -f test.fmt -d test.dat;

DATE FORMAT : YYYY/MM/DD HH:MI:SS:SSSSSS
DATA_NLS_USE: US7ASCII

      Total 3 record download(TEST)

      DOWNLOAD : 911.0000 usec

$ cat test.dat
1,40D930BF000A7566
2,40D930BF000A7566
3,40D930BF000A7566

$ iloader formout -s 127.0.0.1 -u sys -p manager -T TEST2 -f t2_skip_val.fmt;

$ vi t2_skip_val.fmt
table TEST2
{
  "I1" integer;
  "I2" timestamp SKIP 20040623; -> Revised part
}
DATEFORM YYYY/MM/DD HH:MI:SS:SSSSSS
DATA_NLS_USE=US7ASCII

$ iloader in -s 127.0.0.1 -u sys -p manager -f t2_skip_val.fmt -d test.dat;

DATE FORMAT : YYYY/MM/DD HH:MI:SS:SSSSSS
DATA_NLS_USE: US7ASCII

UPLOAD : 13.4300 msec

      Load Count   : 3(TEST2)

```

3.1 About FORM Files

```
iSQL> SELECT * FROM test2;
I1          I2
-----
1          40D8497000000000
2          40D8497000000000
3          40D8497000000000
3 rows selected.
```

4 Troubleshooting and FAQs

4.1 Troubleshooting

4.1.1 Record Upload Failure

Records can fail to be uploaded in a variety of ways, as described below:

- Duplicate data (a primary key or unique index) already exists in the table to which data are to be uploaded.

If duplicate data already exist in the table to which data are to be uploaded, the duplicate data (and only the duplicate data) will be saved in a bad log file, which is set using the “-bad” (bad-file) option, while the remainder of the data, which are not duplicate data, will be uploaded normally. When this problem occurs, the data must be changed manually, or the unique key constraint violation must be resolved and another upload attempt made.

- Record data contain characters used as delimiters.

If characters used as delimiters exist in the record data, the delimiters must be changed to some other set of characters, and another upload attempt made.

- Insufficient space to save data.

If there is not enough database space to save the data, manage the database or the table or perform compaction to secure more free disk space, and then upload data from the point at which the previous upload attempt was interrupted.

- Character data are saved as “?”.

This occurs if the character data can't be expressed using the character set used by the database. The database character set needs to be changed, which is accomplished by creating the database again.

- Only multilingual records fail to be uploaded.

If the character set specified using the ALTIBASE_NLS_USE environment variable is different from the character set in which the records were actually saved, data may not be uploaded normally. In this case, the value of the ALTIBASE_NLS_USE environment variable should be changed to match the character set actually used by the records.

4.1.2 FORM File Parsing Errors

Most FORM file parsing errors are caused by syntax errors that result from editing FORM files manually. Aside from such grammatical errors, similar problems can occur if iLoader reserved words are used as column names or the like.

The following is a list of iLoader reserved words:

ADD	APPEND	BIGINT
BINARY	BIT	BLOB
BOOLEAN	BYTES	CHAR
CLOB	CONDITION	CURRVAL
DATA_NLS_USE	DATE	DATEFORM
DECIMAL	DEFAULT	DOUBLE

DOWNLOAD	EXIT	FLOAT
FORMOUT	GEOMETRY	HELP
HINT	IN	INTEGER
LOG	NCHAR	NCHAR_UTF16
NEXTVAL	NIBBLE	NOEXP
NOLOG	NULL	NUMBER
NUMERIC	NVARCHAR	OUT
QUEUE	QUIT	REAL
REPLACE	SEQUENCE	SKIP
SMALLINT	STRUCTOUT	TABLE
TIMESTAMP	TRUE	TRUNCATE
VARBIT	VARCHAR	YES

4.1.3 Performance Issues

iLoader generally establishes a connection to ALTIBASE HDB using a TCP socket. If the process running iLoader and the ALTIBASE HDB server are running on the same host, it is helpful to use a Unix domain socket or IPC to connect to ALTIBASE HDB. The connection method can be changed by setting the environment variable ISQL_CONNECTION to UNIX or IPC. The details may vary depending on the system.

Ex)

```
sh : $ ISQL_CONNECTION=IPC; export ISQL_CONNECTION
csh: $ setenv ISQL_CONNECTION=IPC
```

When iLoader is used to upload data, it will attempt to commit a transaction for every record. If the -commit option is used to increase the commit interval, upload speed will be affected to some extent. Upload speed increases as the commit interval is increased.

The following shows the changes in speed depending on the commit interval when 100,000 records are uploaded to a disk table.

```
$ time iloader -s 127.0.0.1 -u sys -p manager in -f test.fmt -d test.dat -mode
replace -silent
100000 record load
      UPLOAD: 1519620035
      Load Count : 100000
real 25m29.391s
user 0m7.310s
sys  0m3.930s
```

```
$ time iloader -s 127.0.0.1 -u sys -p manager in -f test.fmt -d test.dat -mode
replace -silent -commit 5000
100000 record load
      UPLOAD: 47475459
      Load Count : 100000
real 0m54.725s
user 0m3.010s
sys  0m2.900s
```

```
$ time iloader -s 127.0.0.1 -u sys -p manager in -f test.fmt -d test.dat -mode
replace -silent -commit 10000
100000 record load
      UPLOAD: 45757975
      Load Count : 100000
real 0m52.652s
user 0m3.240s
sys  0m2.990s
```


4.1 Troubleshooting

Note: If the remote server is specified for the -s option and iSQL is executed, a warning message that the ISQL_CONNECTION setting has been ignored is output and iSQL connects to the remote server, regardless of the value set to the ISQL_CONNECTION environment variable.

4.2 FAQs

- **Q: When I use iLoader with the following FORM file, a parsing error occurs. What is the reason?**

```
table TB_SPEC
{
"CODE" char (6);
"TIME" integer;
"SEQ" integer;
"PROC" integer;
"CONDITION" integer;
}
```

- A: Since CONDITION is a reserved word in ALTIBASE HDB, a parsing error occurs.

- **Q: Whenever I use iLoader to upload data, I receive errors. I want detailed information about the errors. Can you tell me how to get it?**

- A: To obtain such error information, execute iLoader with the option shown below.

```
iloader in -f form.fmt -d data.dat -bad a.bad -log a.log
```

If a file named a.log is specified using the -log option, as shown above, error contents will be written to the file a.log. The format is as follows:

```
[ERR-errno : error_string]
```

This is informative when tracing problems. For reference, if the - bad option is used as shown above, information about failed records is also saved.

- **Q: Can I combine special characters (such as “^” or “|”) with “\n” (line break)?**

- A: Yes, it's possible. The following example shows how to accomplish this.

```
$ iloader formout -s 127.0.0.1 -u sys -p manager -f goods.fmt -T goods -
silent
```

```
$ iloader out -s 127.0.0.1 -u sys -p manager -f goods.fmt -d goods.dat -
r '^%n' -silent
```

```
Total 30 record download(GOODS)
```

```
DOWNLOAD : 876.0000 usec
```

```
$ cat goods.dat
```

```
cat goods.dat
A111100001,IM-300          ,AC0001      ,1000,78000^
A111100002,IM-310          ,DD0001      ,100,98000^
B111100001,NT-H5000        ,AC0002      ,780,35800^
C111100001,IT-U950         ,FA0001      ,35000,7820.55^
C111100002,IT-U200        ,AC0003      ,1000,9455.21^
...
```

- **Q: I tried to download data after adding the following condition clause to the FORM file:**

```
table CUST_PROD
{
"SERV_NO" varchar (10);
"PROD_ID" char (5);
```

4.2 FAQs

```
"EFF_DATE" char (14);
"EXP_DATE" char (14);
"CUST_TYPE" char (2);
"L_MOD_DATE" date;
}
DATEFORM YYYY/MM/DD HH:MI:SS:SSSSSS
DOWNLOAD CONDITION WHERE EXP_DATE >= '20050301000000'
```

The following error occurred, and it would not run.

```
Input Command Parser Error or Reserved Keyword Used
DOWNLOAD: 338
```

- A: When you specify conditions in a download condition clause, you must use double quotation marks (" ").

```
DOWNLOAD CONDITION "WHERE EXP_DATE >= '20050301000000'"
```

This is how you use the quotation marks.

- **Q: I want to sort my data before downloading it. I am wondering whether iLoader supports anything like an ORDER BY clause.**
- A: Data can be sorted by modifying the form file so that it includes a download condition. The data will be sorted according to the column specified in the download condition. The only limitation on this technique is that the column specified in the download condition must be a primary key, or have an index.

Here are the download results before the form file is modified:

```
$ iloader formout -s 127.0.0.1 -u sys -p manager -f dept.fmt -T departments -silent
```

```
$ iloader -s 127.0.0.1 -u sys -p manager out -f dept.fmt -d dept.dat -silent
```

```
Total 8 record download(DEPARTMENTS)
```

```
DOWNLOAD : 908.0000 usec
```

```
$ cat dept.dat
1001,"RESEARCH DEVELOPMENT DEPT 1    ","New York      ",16
1002,"RESEARCH DEVELOPMENT DEPT 2    ","Sydney        ",13
1003,"SOLUTION DEVELOPMENT DEPT      ","Osaka         ",14
2001,"QUALITY ASSURANCE DEPT         ","Seoul         ",17
3001,"CUSTOMER SUPPORT DEPT          ","London        ",4
3002,"PRESALES DEPT                  ","Peking        ",5
4001,"MARKETING DEPT                 ","Brasilia      ",8
4002,"BUSINESS DEPT                  ","Palo Alto     ",7
```

After modifying the FORM file as shown below, the downloaded data will be sorted according to the column specified in the download condition.

```
table DEPARTMENTS
{
"DNO" smallint;
"DNAME" char (30);
"DEP_LOCATION" char (15);
"MGR_NO" integer; -> Not null
}
DOWNLOAD CONDITION "WHERE mgr_no is not null" -> Modified
DATA-NLS_USE=US7ASCII
```

```
$ iloader -s 127.0.0.1 -u sys -p manager out -f dept.fmt -d dept.dat -
silent
```

```
Total 8 record download(DEPARTMENTS)
```

```
DOWNLOAD : 717.0000 usec
```

```
$ cat dept.dat
3001,"CUSTOMER SUPPORT DEPT          ", "London          ",4
3002,"PRESALES DEPT                  ", "Peking           ",5
4002,"BUSINESS DEPT                   ", "Palo Alto        ",7
4001,"MARKETING DEPT                  ", "Brasilia         ",8
1002,"RESEARCH DEVELOPMENT DEPT 2    ", "Sydney           ",13
1003,"SOLUTION DEVELOPMENT DEPT      ", "Osaka            ",14
1001,"RESEARCH DEVELOPMENT DEPT 1    ", "New York         ",16
2001,"QUALITY ASSURANCE DEPT         ", "Seoul            ",17
```

- **Q:** Is there a command I can use to directly upload a text file in which the delimiter is '|'? Mysql has the 'load data infile' command. What commands can I use with your MMDDBMS?
- **A:** You can use the iLoader utility, which allows you to download and upload data on a table-by-table basis. First, use iLoader to create a FORM file corresponding to the table. (You can also use a text editor instead of iLoader.)

```
$ iloader formout -s 127.0.0.1 -u sys -p manager -T test -f test.FORM
```

This is how to upload a text file (delimiter '|'):

```
$ iloader in -s 127.0.0.1 -u sys -p manager -f test.FORM -d datafile -t
'|'
```

In this way, the text file can be directly uploaded.

Note: that the table must already exist.

- **Q:** When the date formats of two columns in the same table are different, is there any way I can import them?
- **A:** In iLoader, DATEFORM can be set for individual columns, as shown in the following example:

```
Ex) Details of FORM file
table table_name
{
column1 date "YYYY-MM-DD";
column2 date;
...
}
DATEFORM YYYY/MM/DD HH:MI:SS:SSSSSS
```

Note that date format options are applied in the following order, in descending order of preference:

1. Date format stated right after the DATE column of a FORM file
2. Environment variable ILO_DATEFORM
3. Date format stated outside of brackets in a FORM file

- **Q:** I want to use iLoader to upload data into a table that already contains data. If I use the **-mode replace** option, will it delete the existing data or truncate it?

4.2 FAQs

- A: It will delete the existing data.
- **Q: The manual says, 'if you want to truncate a large table, it is recommended that you use the iLoader utility to download and upload data.' Does that mean I have to download the data from the table, truncate it with iLoader, and then upload it again with iLoader? And is using the -mode replace option in iLoader different than truncating?**
- A: Since it may take a long time to delete large amounts of data, it is recommended that data be truncated, Data must be downloaded before truncating, and uploaded again after truncating.
- **Q: If I need to add columns to a table while a database is online, how can I go about doing that? Also, I made a backup before changing the schema. Will it be all right if I add columns and then upload a backup file that I made before changing the schema?**
- A: It is possible to change a schema using the ALTER TABLE command, but adding columns is not recommended if a table has many records, because it takes a long time and uses a large amount of memory. In such cases, we recommend that the following steps be taken:
 1. Backup data before changing schema using iLoader
 2. stop replication
 3. drop table from replication
 4. drop table
 5. create table
 6. Use iLoader to upload the backup file saved before changing the schema
 7. add table to replication
 8. Start replication

The FORM file and data file generated before the schema was changed do not contain the information about the added columns. If the added columns have default values, the default values will be inserted, but if they do not have any default values, NULL will be inserted.

- **Q: Is there any way I can import a dmp file exported from Oracle to ALTIBASE HDB as it is?**
- A: Oracle exports are in the binary format. Exported files cannot be imported into ALTIBASE HDB. You must use SQL Loader to access the data. Because the binary format of Oracle cannot be read by other databases, you must use SQL Loader to import the data.
- **Q: Is it possible to upload or download gis data with iLoader? If so, what format are they saved as in the data file?**
- A: Gis data are saved as the Geometry type, which is supported by iLoader. Geometry data stored in data files by iLoader have the WKB (Well Known Bytes) format, which enables them to be saved in the byte order used by the server. WKB data is encoded in CSV format or is stored in a binary format that consists of distinguishable row and column delimiters.

Index

A

Accessing Remote 30
ALTIBASE_NLS_USE 4
Atomic 20

B

batch mode 23

C

Condition Clause Creation 43
Creating form file 23, 29

D

Data Download 24, 30
Data Upload 24, 30
date format 39
DATE FORMAT environment variable 41
direct-path INSERT 21
 considerations 22
 restrictions 22

E

Executing iLoader 29
Execution Result Code 26, 30

H

Help 33

I

iLoader overview 2
Interactive Mode
 interactive mode 29

M

Modifying the form files 38

P

Performance Option 19

R

Remote Access using the Port Number 26

S

sequence 38
specifying date format by column 41

T

TIMESTAMP column 44